

---

# **Magicbot-Z1 SDK Development Documentation**

*Release 1.2.4-doc1*

**MagicLab**

**Dec 22, 2025**



---

## Contents

---

<b>1</b>	<b>About MagicBot Z1</b>	<b>1</b>
1.1	Part Name . . . . .	1
1.2	Dexterous Hand MagicHand S01 . . . . .	3
1.3	Electrical Interface . . . . .	5
1.4	Airborne Computer . . . . .	6
1.5	<b>Field of View of Radar and Camera</b> . . . . .	7
1.6	Joint Motor . . . . .	9
1.7	Degree of Freedom Configuration, Coordinate System, Joint Rotation Axis, and Joint Zero Point . . . . .	10
1.8	Specification Parameters . . . . .	12
<b>2</b>	<b>remote-control</b>	<b>15</b>
2.1	Button Diagram . . . . .	16
2.2	Remote Control Settings . . . . .	17
2.3	Functional Modes . . . . .	17
2.4	Posture Display . . . . .	18
2.5	Charging Instructions . . . . .	18
<b>3</b>	<b>SDK Overview</b>	<b>19</b>
3.1	SDK Communication Interface Introduction . . . . .	19
3.2	Getting the SDK . . . . .	20
<b>4</b>	<b>Software and Hardware Architecture</b>	<b>21</b>
4.1	Software System Architecture Diagram . . . . .	22
4.2	Hardware System Architecture Diagram . . . . .	23
<b>5</b>	<b>Service Introduction</b>	<b>25</b>
<b>6</b>	<b>Quick Start</b>	<b>27</b>
6.1	System Environment . . . . .	27

6.2	Network Environment . . . . .	28
6.3	Installation and Compilation . . . . .	33
6.4	Example Programs . . . . .	33
6.5	Python Example Programs . . . . .	34
6.6	Others . . . . .	38
<b>7</b>	<b>Robot Main Control Service (C++)</b>	<b>41</b>
7.1	Interface Definition . . . . .	41
<b>8</b>	<b>High-Level Motion Control Service (C++)</b>	<b>47</b>
8.1	Interface Definition . . . . .	47
8.2	Type Definitions . . . . .	50
8.3	Enumeration Type Definitions . . . . .	50
8.4	Joystick Diagram . . . . .	52
8.5	Head Movement Range Diagram . . . . .	53
8.6	High-Level Motion Control Robot State Introduction . . . . .	53
8.7	High-Level Motion Control Interface . . . . .	54
<b>9</b>	<b>Low-Level Motion Control Service (C++)</b>	<b>57</b>
9.1	Interface Definition . . . . .	57
9.2	Type Definitions . . . . .	63
9.3	URDF Reference . . . . .	67
9.4	Low-Level Motion Control Robot State Introduction . . . . .	67
9.5	Notice: . . . . .	68
<b>10</b>	<b>Sensor Control Service (C++)</b>	<b>69</b>
10.1	Interface Definition . . . . .	69
10.2	Type Definitions . . . . .	74
10.3	Notice: . . . . .	76
<b>11</b>	<b>Audio Control Service (C++)</b>	<b>77</b>
11.1	Interface Definition . . . . .	77
11.2	Type Definitions . . . . .	82
11.3	Structure Definitions . . . . .	82
11.4	DOA . . . . .	84
11.5	Notice: . . . . .	84
<b>12</b>	<b>State Monitor Service (C++)</b>	<b>85</b>
12.1	Interface Definition . . . . .	85
12.2	Error Code Mapping Table . . . . .	88
<b>13</b>	<b>SLAM Navigation Control Service (C++)</b>	<b>91</b>
13.1	Interface Definition . . . . .	91
13.2	Type Definitions . . . . .	100

13.3	Enumeration Type Definitions . . . . .	101
13.4	SLAM Navigation Control Introduction . . . . .	102
<b>14</b>	<b>Robot Main Control Service (Python)</b>	<b>105</b>
14.1	Interface Definition . . . . .	105
<b>15</b>	<b>High-Level Motion Control Service (Python)</b>	<b>111</b>
15.1	Interface Definition . . . . .	111
15.2	Type Definitions . . . . .	114
15.3	Enumeration Type Definitions . . . . .	114
15.4	Joystick Diagram . . . . .	116
15.5	Head Movement Range Diagram . . . . .	117
15.6	High-Level Motion Control Robot State Introduction . . . . .	117
15.7	High-Level Motion Control Interface . . . . .	118
<b>16</b>	<b>Low-Level Motion Control Service (Python)</b>	<b>121</b>
16.1	Interface Definition . . . . .	121
16.2	Type Definitions . . . . .	127
16.3	URDF Reference . . . . .	131
16.4	Low-Level Motion Control Robot State Introduction . . . . .	131
16.5	Notice: . . . . .	131
<b>17</b>	<b>Sensor Control Service (Python)</b>	<b>133</b>
17.1	Interface Definition . . . . .	133
17.2	Data Types . . . . .	138
17.3	Notice: . . . . .	140
<b>18</b>	<b>Audio Control Service (Python)</b>	<b>141</b>
18.1	Interface Definition . . . . .	141
18.2	Type Definitions . . . . .	145
18.3	Structure Definitions . . . . .	146
18.4	DOA . . . . .	147
18.5	Notice: . . . . .	148
<b>19</b>	<b>State Monitor Service (Python)</b>	<b>149</b>
19.1	Interface Definition . . . . .	149
19.2	Error Code Mapping Table . . . . .	152
<b>20</b>	<b>SLAM Navigation Control Service (Python)</b>	<b>155</b>
20.1	Interface Definition . . . . .	155
20.2	Type Definitions . . . . .	164
20.3	Enumeration Type Definitions . . . . .	166
20.4	SLAM Navigation Control Introduction . . . . .	166

<b>21 High-Level Motion Control Example</b>	<b>169</b>
21.1 C++:	169
21.2 Python	176
21.3 Running Instructions	186
<b>22 Low-Level Motion Control Example</b>	<b>189</b>
22.1 C++:	189
22.2 Python	193
22.3 Running Instructions	202
<b>23 Sensor Control Example</b>	<b>203</b>
23.1 C++	203
23.2 Python	218
23.3 Running Instructions	234
<b>24 Audio Control Example</b>	<b>237</b>
24.1 C++	237
24.2 Python	246
24.3 Running Instructions	259
<b>25 State Monitor Example</b>	<b>261</b>
25.1 C++	261
25.2 Python	263
25.3 Running Instructions	267
<b>26 SLAM Navigation Example</b>	<b>269</b>
26.1 C++	269
26.2 Python	296
26.3 Running Instructions	335
<b>27 FAQ</b>	<b>339</b>
27.1 Development Environment Preparation	339
27.2 Does Magicbot-Z1 support wireless development?	339
27.3 What is the current low-level communication frequency of Magicbot-Z1?	339
27.4 Unable to Subscribe and Publish Topic Data?	340
27.5 SDK subscription topic data rate unstable?	340
27.6 SDK API Call Error: Deadline Exceeded	341
27.7 How to View SDK Internal Configuration and Logs?	341
27.8 Video Streaming	341
27.9 SLAM Relocation Failed?	341
27.10 SLAM Navigation Not Executing?	342
27.11 Runtime Error: Invalid IP address	342
27.12 Log Error: Call of pthread_setschedparam with insufficient privileges!	342

27.13	connect Error: Failed to connect to robot, code: ErrorCode.SERVICE_ERROR, message: failed to connect to all addresses; last error: UNKNOWN: ipv4:192.168.54.119:50051: Failed to connect to remote host: Connection refused ...	342
27.14	Trick Execution Error: Failed to execute robot trick, code: ErrorCode.SERVICE_ERROR, message: 优先级过低 .....	343
27.15	Trick Execution Error: Failed to execute robot trick, code: ErrorCode.SERVICE_ERROR, message: 危险动作 .....	343
27.16	Trick Execution Error: Failed to execute robot trick, code: ErrorCode.SERVICE_ERROR, message: 调用 ROS2 服务失败 .....	343





# CHAPTER 1


---

## About MagicBot Z1


---

### 1.1 Part Name

The MagicBot Z1 whole body is divided into upper and , with multiple degrees of freedom. The head has 1 degree of freedom (Yaw). A single arm has 5+ degrees of freedom, including shoulder-body joint, upper arm joint, elbow joint, and wrist joint (optional). A single leg has 6 degrees of freedom, including hip joint, leg joint, hip joint, knee joint, and ankle joint. The waist has 1 degree of freedom (Yaw). Depending on the version, the whole body can be divided into the Z1 basic version with 24 degrees of freedom, and the Z1 development version with an optional 24-50 degrees of freedom. Having multiple joint motor degrees of freedom enables the robot to achieve precise motion and posture control. The MagicBot Z1\_24 degrees of freedom humanoid robot body is shown in the figure below, and please refer to the physical product for details.



## 1.2 Dexterous Hand MagicHand S01




MagicHand S01 Specifications	
Length, Width, and Depth	200mm x 87mm x 55mm
Weight	≤650g
Rating	5
Total Degrees of Freedom (Number of Joints)	11
Active Degrees of Freedom (Number of Motors)	61, Active Degrees of Freedom for Common Fingers: 22, Active Degrees of Freedom for Thumb: 1
Joint Angles	Common Fingers Flexion: 13° to 203°; Thumb Flexion: -9° to 66.6°; Thumb Lateral Pendulum: 71° to 180°.
Drive mode	Coreless motor + reduction gearbox + T-type screw
Transmission mode	Connecting rod transmission
Actuation options	Pinching, grasping, pressing, lifting, pushing, and other anthropomorphic actions
Operating voltage	DC12V
Quiescent current	0.1A @12V
Maximum current	3A@12V
Proximity Sensing Solution	ToF
Number of Tactile Sensors	5
Tactile Sensor Dimensions	Normal Force, Tangential Force
Tactile Sensor Resolution*	0.1N
Tactile Sensor Range	0.1-10N
Single-Finger Grip Strength*	2.5kg
Four-Finger Grip Strength*	9.1kg
Total Hand Load*	5kg
End-of-Hand Repeatability*	0.1mm
Opening and Closing Time*	1.2s
Thumb Lateral Swing Speed*	112°/s
Thumb Flexion Speed*	106°/s
Four-Finger Flexion Speed*	150°/s
Communication Interface	RS485, EtherCAT
SDK Language	C++
Durability Lifespan*	More than 100,000 times

\*Parameters such as single-finger grip strength, four-finger grip strength, and whole-hand load were measured in a laboratory environment.

\*The above parameters may vary under different business scenarios and device configurations. Please refer to the actual usage experience.

## 1.3 Electrical Interface

The back of MagicBot Z1 is equipped with electrical interfaces, which are used to connect various body joint motors, sensor peripherals, network ports, etc. This design allows you to conveniently perform debugging, troubleshooting, and secondary development.



Serial Number	Interface Type	Interface Name	Instructions for Use
1	button	Remote control matching	Press and hold this button, the remote control will turn on and start pairing. The buzzer of the remote control will beep to complete the configuration, then release the button. For details, please refer to the user manual of the remote control.
2	button	Wireless Emergency Stop Matching	Press briefly 3 times to enter pairing mode. Press any key on the remote control to successfully complete the pairing.
3	button	Bluetooth Network Pairing Button	Press briefly once to enter Bluetooth pairing mode
4	Type-C	Type-C USB3.0	Supports USB3.0 Host, with a maximum output of 5V/1.5A
5	Type-C	Type-C USB3.0	Supports USB3.0 Host, with a maximum output of 5V/1.5A
6	Type-C	Type-C USB3.0	Supports USB3.0 Host, with a maximum output of 5V/1.5A
7	Type-C	Type-C USB3.0	Supports USB3.0 Host, with a maximum output of 5V/1.5A
8	XT30PV M30.G.	VBAT	Directly connected battery output, voltage 54V, current recommended not to exceed 5A. Pay attention to the positive and negative poles
9	RJ45	1000Base-T	Supports 10/100/1000Mbps, supports debugging
10	RJ45	1000Base-T	Supports 10/100/1000Mbps, supports debugging

## 1.4 Airborne Computer

MagicBot Z1 comes standard with 1 [Motion Control Computing Unit] and 1 [Development Computing Unit] on board.

Parameter	Develop computing unit
Model	Jetson Orin NX
CPU	Arm® Cortex®-A78AE
Number of Cores	8
Number of Threads	8
Max Turbo Frequency	2GHz
Video Memory	16G
Memory	16G
Cache	2MB L2 + 4MB L3
Storage	512G
GPU	1024-core NVIDIA Ampere architecture GPU with 32 Tensor Cores
Maximum Dynamic Frequency of Graphics Card	918MHz
Gaussian and Neural Accelerator	3
Instruction Set Architecture	64bit
OpenGL	4.6
OpenGL ES	3.2
Vulkan™	1.1
CUDA	11.4


【Motion Control Computing Unit】is dedicated to the magic atom motion control program and is not open to the public. Developers can only use the 【Development Computing Unit】 for secondary development.

## 1.5 Field of View of Radar and Camera

The MagicBot Z1 is equipped with a LIVOX-MID360 lidar on its head, providing the robot with excellent environmental perception capabilities. The lidar uses an all-round, full-angle scanning technology, with a horizontal FOV of up to 360° and a maximum vertical FOV of 49°, enabling it to obtain accurate environmental data in real time. It can quickly identify and measure surrounding objects, providing high-resolution point cloud data.


The Z1 head is equipped with a D435i depth camera (FOV horizontal 87°, vertical 58°) and a binocular fisheye camera (FOV horizontal 135°, vertical 75°). This provides the robot with excellent visual perception capabilities, enabling it to more accurately perceive and understand the surrounding environment, achieve precise spatial perception and obstacle detection, and allowing the robot to interact with the environment more intelligently and flexibly and handle various scenarios.

Field of View Image 1



MID360 FOV


Field of View Image 2




D435 depth camera FOV



Field of View Image 3



Field of View Image 4




## 1.6 Joint Motor

The joints of MagicBot Z1 are equipped with Magic Atom's full stack self-developed motors, which have excellent performance and features. The maximum torque of the motor is 130 N.m, and the motor structure is lightweight and compact. The motor is also equipped with dual encoders, providing more accurate position and speed feedback to meet the requirements of high-precision control. Joint sequence names and joint limits

Joint number	Joint name	Limit (radians)
1	left_hip_pitch_joint	-2.7925~2.7925
2	left_hip_roll_joint	-0.524~2.967
3	left_hip_yaw_joint	-2.7925~2.7925
4	left_knee_joint	0~2.653
5	left_ankle_pitch_joint	-0.83~0.524
6	left_ankle_roll_joint	-0.262~0.262
7	right_hip_pitch_joint	-2.7925~2.7925
8	right_hip_roll_joint	-2.967~0.524
9	right_hip_yaw_joint	-2.7925~2.7925
10	right_knee_joint	0~2.653
11	right_ankle_pitch_joint	-0.83~0.524
12	right_ankle_roll_joint	-0.262~0.262
13	left_shoulder_pitch_joint	-2.88~2.88
14	left_shoulder_roll_joint	-0.175~2.2515
15	left_shoulder_yaw_joint	-2.618~2.618
16	left_elbow_joint	-0.96~1.70
17	left_wrist_yaw_joint	-2.618~2.618
18	right_shoulder_pitch_joint	-2.88~2.88
19	right_shoulder_roll_joint	-2.2515~0.175
20	right_shoulder_yaw_joint	-2.618~2.618
21	right_elbow_joint	-0.96~1.70
22	right_wrist_yaw_joint	-2.618~2.618

## 1.7 Degree of Freedom Configuration, Coordinate System, Joint Rotation Axis, and Joint Zero Point

When all joints are at zero degrees, the coordinate systems are as shown in the figure below. Red represents the x-axis, green represents the y-axis, and blue represents the z-axis.



## 1.8 Specification Parameters

### 1.8.1 Mechanical Parameters

Category	Z1	Z1 Development Edition
Height, Width, and Depth (Standing)	1369422200mm	1369422200mm
Height, Width, and Depth (Folded)	730422395mm	730422395mm
Weight with battery	Approximately 40kg	Approximately 40kg+
Total degrees of freedom (number of joints)	24	24 - 50
Single-leg degrees of freedom	6	6
Head degrees of freedom	1	1
Waist degrees of freedom	1	1
Single Arm DOF	5	5+ (2 wrist DOF optional)
Dexterous Hand DOF	/	Optional 11-DOF Haptic Dexterous Hand
Joint Output Bearing	Industrial-grade high-rigidity roller bearing (can withstand 8.7 kN impact force)	Industrial-grade high-rigidity roller bearing (can withstand 8.7 kN impact force)
Joint Motor	Low-inertia, high-speed, high-overload permanent magnet synchronous motor (control frequency 25kHz, high burst force, improved heat dissipation)>	Low inertia, high speed, high overload permanent magnet synchronous motor (control frequency 25kHz, high burst force, improved heat dissipation)
Maximum knee torque*	100N.m	130N.m
Maximum arm load*	2kg	3kg

Category	Z1	Z1 Development Edition
Calf + thigh length	0.6m	0.6m
Arm span	Approximately 0.5m	Approximately 0.5m
Head Z-axis joint range of motion	$\pm 40^\circ$	$\pm 40^\circ$
Waist Z-axis joint range of motion	$\pm 160^\circ$	$\pm 160^\circ$
Knee joint range of motion	0-152°,	0-152°,
Hip joint range of motion	P $\pm 160^\circ$ , R -30~+110°, Y $\pm 160^\circ$	P $\pm 160^\circ$ , R -30~+110°, Y $\pm 160^\circ$

## 1.8.2 Electrical Characteristics

Category	Z1	Z1 Development Edition
Joint Encoder	Dual Encoder	Dual Encoder
Cooling System	Intelligent Air Cooling	Intelligent Air Cooling
Power Supply	15-cell Battery	15-cell Battery
Basic Computing Power	8-core High-Performance CPU	8-core High-Performance CPU
Perception Sensors:	3D LiDAR + Depth Camera + Binocular Fisheye Camera + Head Tactile Sensor	3D LiDAR + Depth Camera + Binocular Fisheye Camera + Head Tactile Sensor
WiFi6, Bluetooth 5.2	Yes	Yes
Microphone Array	Yes	Yes
5W Speaker	Yes	Yes

## 1.8.3 Supporting Equipment

Category	Z1	Z1 Development Edition
High Computing Power Module	No	Optional
Smart Battery (Quick Release)	10000mAh	10000mAh
Charger	62V 5A	62V 5A
Handheld Remote Control	Yes	Yes

## 1.8.4 Other

Category	Z1	Z1 Development Edition
Battery Life	Approximately 2 hours	Approximately 2 hours
OTA Upgrade	Supported	Supported
Secondary Development	No	Yes

\*Maximum torque, maximum arm load, endurance time, etc. are measured under laboratory conditions.

\*The above parameters may vary under different business scenarios and device configurations. Please refer to the actual usage experience.

## CHAPTER 2


---

remote-control

---

---

## 2.1 Button Diagram





## 2.2 Remote Control Settings

Remote Control Settings	Buttons/Operations
Remote Control Power On	Press Home Button
Remote Control Power Off	Back + B, press and hold for 3 seconds; it will automatically shut down (lights off) after a period of inactivity.
Pairing the Remote Control with the Robot	Approaching the robot will automatically pair it. The remote control will vibrate once upon successful pairing; if pairing fails, the indicator light will flash red rapidly.
Gaining Control of the Robot	Press Home + Start buttons
Releasing Control of the Robot	Press Home + Back buttons

Note: The remote control communicates with the robot via 2.4G. The corresponding indicator light is red. If yellow, blue, green, or other colors appear, the remote control's mode is incorrect. The mode switch needs to be moved to the far left on the back, as shown in the button diagram.

## 2.3 Functional Modes

Functional Modes	Buttons
Standing in Place 1	LT+RT + A
Posture Display 2	LT+RT + B
Human Walking 3	LT+RT + X
Human Running 4	LT+RT + Y

Hanger power on: Power on -> 1 -> Demo -> 1 -> Power off. The demonstration is divided into posture display and anthropomorphic walking/running.

## 2.4 Posture Display

Posture Display	Buttons
Welcome	LT+A
Shake head	LT+B
Greeting (Left hand)	LT+X
Greeting (Right hand)	LT+Y
Shake hands - Left hand - Extend hand	LB+A
Shake hands - Left hand - Withdraw hand	LB+B
Shake hands - Right hand - Extend hand	LB+X
Shake hands - Right hand - Withdraw hand	LB+Y
Left turn introduction - High	RB+A
Left turn introduction - Low	RB+B
Right Turn Introduction - High	RB+X
Right Turn Introduction - Low	RB+Y


Note: When displaying the postures in the table above, you must first enter posture 2 display mode.

## 2.5 Charging Instructions

Battery Status	Indicator Light Effects
Battery less than 20%	Red flashing indicator
Charging in progress	Red breathing (slow flashing)
Charging complete with power on	Solid red light
Charging complete with power off	Red solid light will turn off after 7 seconds

Note: Remote control via Type-C Charge using the charging cable.

### 3.1 SDK Communication Interface Introduction



- Current software version does not support GST video stream transmission

Z1 uses LCM/GRPC/UDP/ZMQ as message middleware, with main data interaction modes: topics (subscribe/publish) and RPC (request/response)

- **Topics (Subscribe/Publish):** Receivers subscribe to specific messages, senders send messages to receivers based on subscription lists, mainly used for medium-high frequency or continuous data interaction.
- **RPC (Request/Response):** Question-answer mode, implementing data acquisition or operations through requests. Used for low-frequency or data interaction during function switching.

Main calling methods for topics and RPC interfaces: functional interfaces

- **Functional Interface:** Encapsulates API calls into function calls for user convenience.

## 3.2 Getting the SDK

**magicbot-z1\_sdk** is Magic Lab's next-generation robot Z1 development SDK. The SDK encapsulates high-level motion control, low-level motor control, voice control and other interfaces, and provides related functional interfaces. You can refer to our provided SDK tutorials to learn robot control and complete Z1 secondary development;

### 3.2.1 SDK Download Address:

`magicbot-z1_sdk`

- The SDK version must be aligned with the robot firmware version. Please refer to [ChangeLog](#)
- For downloading the SDK PDF documentation, please refer to: [PDF](#)

### 3.2.2 URDF/MJCF Download Address:

[URDF/MJCF](#)

## CHAPTER 4


---

### Software and Hardware Architecture


---

---

## 4.1 Software System Architecture Diagram




## 4.2 Hardware System Architecture Diagram







## Service Introduction



Magicbot Z1 provides the following services through message middleware (LCM/GRPC/UDP/ZMQ):

- **High-Level Motion Control Service**

Based on Z1's built-in gait controller, it can perform gait switching, trick execution, attitude and velocity control (equivalent to remote control) and other functions. High-level motion control service uses GRPC for communication.

- **Low-Level Motion Control Service**

Through service interfaces, joint and IMU data can be obtained in real-time, and joint commands can be sent in real-time to control motors. Low-level motion control service uses LCM for communication.

- **Audio Service**

Through service interfaces, volume and voice control can be managed. Audio service uses GRPC/LCM for communication.

- **Sensor Service**

Supports data subscription for lidar, RGBD, binocular camera and other sensors. Sensor service uses GRPC/UDP/LCM/ZMQ for communication.

Notice: Current version only supports lidar data subscription, RGBD/binocular camera data is not yet supported

- **Status Monitoring Service**

Through service interfaces, robot body software/hardware faults and BMS status can be subscribed to. Status monitoring service uses LCM for communication.

- **SLAM Navigation Service**

Robot SLAM mapping and navigation control can be performed through service interfaces. SLAM navigation service uses GRPC/LCM for communication.

---

## 6.1 System Environment

Development is recommended on Ubuntu 22.04 system. Mac/Windows systems are not currently supported for development. The robot's onboard PC runs official services and does not support development;

APP and SDK cannot support control the robot simultaneously

### 6.1.1 Development Environment Requirements

- GCC  $\geq$  11.4 (for Linux)
- CMake  $\geq$  3.16
- Make build system
- C++20 (minimum)
- Eigen3
- python3.10

### 6.1.2 System Configuration

First, to achieve real-time communication under regular users, add the following configuration to the `/etc/security/limits.conf` file:

```
*      -   rtprio    98
```

Second, to increase the receive buffer for each socket connection, add the following configuration to the `/etc/sysctl.conf` file. Use `sudo sysctl -p` to take effect immediately or restart to take effect:


```
net.core.rmem_max=20971520
net.core.rmem_default=20971520
net.core.wmem_max=20971520
net.core.wmem_default=20971520
```

## 6.2 Network Environment


Connect the user computer and robot switch to a unified network. It is recommended that new users use an Ethernet cable to connect the user computer to the robot switch, and set the network card communicating with the robot to the 192.168.54.X network segment, recommended 192.168.54.111. Experienced users can configure the network environment themselves.

### 6.2.1 Configuration Steps

1. Connect one end of the Ethernet cable to the robot and the other end to the user computer. The robot's onboard computer IP addresses are 192.168.54.110 (cerebellum computing board) and 192.168.54.119 (brain computing board), so the computer IP needs to be set to the same network segment, recommended 192.168.54.111.



2. To test if the communication connection is normal, you can test with ping:

A terminal window with a title bar that reads "eame@debian: ~ 64x24". The terminal shows a user prompt "editorxu@09:38:37:~\$" followed by the command "ping 192.168.54.110". The output of the command is displayed in several lines, showing the results of nine ping attempts. Each line indicates that 64 bytes of data were received from the target IP address, with the sequence number (icmp\_seq) increasing from 1 to 9, and the time taken for each ping is listed in milliseconds. The times vary slightly, ranging from approximately 0.298 ms to 0.424 ms.

```
eame@debian: ~ 64x24
editorxu@09:38:37:~$ ping 192.168.54.110
PING 192.168.54.110 (192.168.54.110) 56(84) bytes of data.
64 bytes from 192.168.54.110: icmp_seq=1 ttl=64 time=0.298 ms
64 bytes from 192.168.54.110: icmp_seq=2 ttl=64 time=0.348 ms
64 bytes from 192.168.54.110: icmp_seq=3 ttl=64 time=0.309 ms
64 bytes from 192.168.54.110: icmp_seq=4 ttl=64 time=0.361 ms
64 bytes from 192.168.54.110: icmp_seq=5 ttl=64 time=0.424 ms
64 bytes from 192.168.54.110: icmp_seq=6 ttl=64 time=0.349 ms
64 bytes from 192.168.54.110: icmp_seq=7 ttl=64 time=0.318 ms
64 bytes from 192.168.54.110: icmp_seq=8 ttl=64 time=0.386 ms
64 bytes from 192.168.54.110: icmp_seq=9 ttl=64 time=0.300 ms
```

3. Check the network card name corresponding to the 192.168.54.111 address by using the `ifconfig` command to view the network card name, as shown in the figure:

```
eame@debian: ~/ws/hal_driver/build/install/bin
eame@debian: ~/ws/hal_driver/build/install/bin 92x48
editorxu@11:35:09:~$ ifconfig
docker0: flags=4099<UP,BROADCAST,MULTICAST> mtu 1500
    inet 172.17.0.1 netmask 255.255.0.0 broadcast 172.17.255.255
    ether 02:42:a5:79:70:7c txqueuelen 0 (Ethernet)
    RX packets 0 bytes 0 (0.0 B)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 0 bytes 0 (0.0 B)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

enp0s31f6: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.54.111 netmask 255.255.255.0 broadcast 192.168.54.255
    inet6 fe80::4424:e003:4c15:2055 prefixlen 64 scopeid 0x20<link>
    ether 84:ba:59:72:ea:08 txqueuelen 1000 (Ethernet)
    RX packets 1042289 bytes 354005321 (354.0 MB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 1050126 bytes 280690787 (280.6 MB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
    device interrupt 16 memory 0x82200000-82220000

lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
    inet 127.0.0.1 netmask 255.0.0.0
    inet6 ::1 prefixlen 128 scopeid 0x10<host>
    loop txqueuelen 1000 (Local Loopback)
    RX packets 87371077 bytes 9065855211 (9.0 GB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 87371077 bytes 9065855211 (9.0 GB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

virbr0: flags=4099<UP,BROADCAST,MULTICAST> mtu 1500
    inet 192.168.122.1 netmask 255.255.255.0 broadcast 192.168.122.255
    ether 52:54:00:9e:77:df txqueuelen 1000 (Ethernet)
    RX packets 0 bytes 0 (0.0 B)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 0 bytes 0 (0.0 B)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

wlp0s20f3: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 172.29.41.197 netmask 255.255.252.0 broadcast 172.29.43.255
    inet6 fe80::4eb3:a694:2eba:ac34 prefixlen 64 scopeid 0x20<link>
    ether 5c:b4:7e:8f:79:97 txqueuelen 1000 (Ethernet)
    RX packets 26672293 bytes 13099885890 (13.0 GB)
    RX errors 0 dropped 101 overruns 0 frame 0
    TX packets 20349743 bytes 3661275993 (3.6 GB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

Assuming the network port connecting the SDK secondary development PC to the robot is `enp0s31f6`, the following configuration is needed for SDK to communicate with the robot at the low level:

```
sudo ifconfig enp0s31f6 multicast
sudo route add -net 224.0.0.0 netmask 240.0.0.0 dev enp0s31f6
```

To avoid having to manually reconfigure the network interface multicast route every time you unplug and replug the network cable, you can automate this process on your development PC by following the steps below (system requirements: Ubuntu 22.04, and NetworkManager as the network configuration tool):

- Check the service status:

```
$ systemctl is-active NetworkManager
active
```

If the output shows `active`, proceed with the next steps; otherwise, skip the following steps.

- Edit the configuration file with the command: `sudo vim /etc/NetworkManager/dispatcher.d/90-add-mcast-route:`

```
#!/bin/bash

IFACE="$1"
STATUS="$2"

# Target network interface
TARGET_IF="enp0s31f6"

# Only execute when the specified interface is 'carrier on' or 'up'
if [ "$IFACE" = "$TARGET_IF" ] && [ "$STATUS" = "up" || "$STATUS" = "carrier" ];
→ then
    # Delete any possible old route
    ip route del 224.0.0.0/4 dev "$TARGET_IF" 2>/dev/null

    # Add the required route (with scope link)
    ip route add 224.0.0.0/4 dev "$TARGET_IF" scope link
fi
```

- Add execute permission:

```
sudo chmod +x /etc/NetworkManager/dispatcher.d/90-add-mcast-route
```

- Restart the service to take effect:

```
sudo systemctl restart NetworkManager
```

Check if the network interface route is configured correctly:

```
$ ip route | grep 224.0.0.0
224.0.0.0/4 dev enp0s31f6 scope link
```



## 6.3 Installation and Compilation

The following steps assume the working directory is `/home/magicbot/workspace`

### 6.3.1 Install magicbot-z1\_sdk:

Installation steps: Enter the `magicbot-z1_sdk` directory and execute the following commands step by step to install the SDK to the `/opt/magic_robotics/magicbot_z1_sdk` directory for easy `find_package` retrieval for secondary development program compilation and linking:

```
cd /home/magicbot/workspace/magicbot-z1_sdk/  
mkdir build  
cd build  
cmake .. -DCMAKE_INSTALL_PREFIX=/opt/magic_robotics/magicbot_z1_sdk  
sudo make install
```

### 6.3.2 Example Compilation

Compilation steps: Enter the `magicbot-z1_sdk` directory and execute the following commands step by step to generate example executable programs in the build directory:

```
cd /home/magicbot/workspace/magicbot-z1_sdk/  
mkdir build  
cd build  
cmake .. -DBUILD_EXAMPLES=ON  
make -j8
```

## 6.4 Example Programs

In the `magicbot-z1_sdk/build` directory:

- **Audio Example:**
  - `audio_example`
- **Sensor Example:**
  - `sensor_example`
- **Status Monitoring Example:**
  - `monitor_example`
- **Low-Level Motion Control Example:**
  - `low_level_motion_example`

- **High-Level Motion Control Example:**

- high\_level\_motion\_example

- **SLAM Example:**

- slam\_example

- **Navigation Example:**

- navigation\_example

**Notice:** Among these, the high-level motion control examples have sequential dependencies (recovery stand -> balance stand -> execute trick actions/remote control)

### 6.4.1 Enter Debug Mode:

Follow the operation procedures to ensure the robot enters debug mode

### 6.4.2 Run Examples

Enter the magicbot-z1\_sdk/build directory and execute the following commands:

```
cd /home/magicbot/workspace/magicbot-z1_sdk/build
# Environment configuration
sudo ifconfig enp0s31f6 multicast
sudo route add -net 224.0.0.0 netmask 240.0.0.0 dev enp0s31f6
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH

# execute audio control example
./audio_example
```

## 6.5 Python Example Programs

In the magicbot-z1\_sdk/example/python directory:

- **Audio Example:**

- audio\_example.py

- **Sensor Example:**

- sensor\_example.py

- **Status Monitoring Example:**

- monitor\_example.py

- **Low-Level Motion Control Example:**

- low\_level\_motion\_example.py

- **High-Level Motion Control Example:**

- high\_level\_motion\_example.py

- **SLAM Example:**

- slam\_example.py

- **Navigation Example:**

- navigation\_example.py

**Notice:** Among these, the high-level motion control examples have sequential dependencies (recovery stand -> balance stand -> execute trick actions/remote control)

### 6.5.1 Enter Debug Mode:

Follow the operation procedures to ensure the robot enters debug mode

### 6.5.2 Run Examples

Enter the magicbot-z1\_sdk/example/python directory and execute the following commands:

```
cd /home/magicbot/workspace/magicbot-z1_sdk/example/python
# Environment configuration
sudo ifconfig enp0s31f6 multicast
sudo route add -net 224.0.0.0 netmask 240.0.0.0 dev enp0s31f6
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH

# execute audio control example
python3 audio_example.py
```

Get Python API help information:

```
# Environment configuration
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH

$ python3
Python 3.10.12 (main, Aug 15 2025, 14:32:43) [GCC 11.4.0] on linux
Type "help", "copyright", "credits" or "license" for more information.
# Import Magic Z1 python SDK interface
>>> import magicbot_z1_python
# View all interface information
>>> help(magicbot_z1_python)
```

(continues on next page)

(continued from previous page)

```
# View CameraInfo structure information
>>> help(magicbot_z1_python.CameraInfo)
# View HighLevelMotionController object information
>>> help(magicbot_z1_python.HighLevelMotionController)
# View LowLevelMotionController object information
>>> help(magicbot_z1_python.LowLevelMotionController)
# View SensorController object information
>>> help(magicbot_z1_python.SensorController)
# View AudioController object information
>>> help(magicbot_z1_python.AudioController)
# View StateMonitor object information
>>> help(magicbot_z1_python.StateMonitor)
```

For example, if you want to view the TrickAction enumeration values:

```
$ python3
Python 3.10.12 (main, Aug 15 2025, 14:32:43) [GCC 11.4.0] on linux
Type "help", "copyright", "credits" or "license" for more information.
>>> import magicbot_z1_python
>>> help(magicbot_z1_python.TrickAction)
Help on class TrickAction in module magicbot_z1_python:

class TrickAction(pybind11_builtins.pybind11_object)
|   Method resolution order:
|       TrickAction
|       pybind11_builtins.pybind11_object
|       builtins.object
|
|   Methods defined here:
|
|   __eq__(...)
|       __eq__(self: object, other: object, /) -> bool
|
|   __getstate__(...)
|       __getstate__(self: object, /) -> int
|
|   __hash__(...)
|       __hash__(self: object, /) -> int
|
|   __index__(...)
```

(continues on next page)

(continued from previous page)

```
|     __index__(self: magicbot_z1_python.TrickAction, /) -> int
|
|     __init__(...)
|     __init__(self: magicbot_z1_python.TrickAction, value: typing.SupportsInt) ->
↳None
|
|     __int__(...)
|     __int__(self: magicbot_z1_python.TrickAction, /) -> int
|
|     __ne__(...)
|     __ne__(self: object, other: object, /) -> bool
|
|     __repr__(...)
|     __repr__(self: object, /) -> str
|
|     __setstate__(...)
|     __setstate__(self: magicbot_z1_python.TrickAction, state: typing.SupportsInt,
↳/) -> None
|
|     __str__(...)
|     __str__(self: object, /) -> str
|
|     -----
|     Readonly properties defined here:
|
|     __members__
|
|     name
|         name(self: object, /) -> str
|
|     value
|
|     -----
|     Data and other attributes defined here:
|
|     ACTION_LEFT_GREETING = <TrickAction.ACTION_LEFT_GREETING: 300>
|
|     ACTION_NONE = <TrickAction.ACTION_NONE: 0>
|
|     ACTION_RIGHT_GREETING = <TrickAction.ACTION_RIGHT_GREETING: 301>
```

(continues on next page)

(continued from previous page)

```
|
| ACTION_SHAKE_HEAD = <TrickAction.ACTION_SHAKE_HEAD: 220>
|
| ACTION_SHAKE_LEFT_HAND_REACHOUT = <TrickAction.ACTION_SHAKE_LEFT_HAND...
|
| ACTION_SHAKE_LEFT_HAND_WITHDRAW = <TrickAction.ACTION_SHAKE_LEFT_HAND...
|
| ACTION_SHAKE_RIGHT_HAND_REACHOUT = <TrickAction.ACTION_SHAKE_RIGHT_HAN...
|
| ACTION_SHAKE_RIGHT_HAND_WITHDRAW = <TrickAction.ACTION_SHAKE_RIGHT_HAN...
|
| ACTION_TRUN_LEFT_INTRODUCE_HIGH = <TrickAction.ACTION_TRUN_LEFT_INTROD...
|
| ACTION_TRUN_LEFT_INTRODUCE_LOW = <TrickAction.ACTION_TRUN_LEFT_INTRODU...
|
| ACTION_TRUN_RIGHT_INTRODUCE_HIGH = <TrickAction.ACTION_TRUN_RIGHT_INTR...
|
| ACTION_TRUN_RIGHT_INTRODUCE_LOW = <TrickAction.ACTION_TRUN_RIGHT_INTRO...
|
| ACTION_WELCOME = <TrickAction.ACTION_WELCOME: 340>
|
| -----
| Static methods inherited from pybind11_builtins.pybind11_object:
|
| __new__(*args, **kwargs) from pybind11_builtins.pybind11_type
|     Create and return a new object. See help(type) for accurate signature.
```

## 6.6 Others

### 6.6.1 SDK Configuration File

The SDK will generate its default configuration file in the /tmp directory by default during runtime. If the configuration file already exists, it will use the existing configuration:

```
$ ls /tmp/magicbot_z1_mjrrt.yaml
/tmp/magicbot_z1_mjrrt.yaml
```

## 6.6.2 SDK Logs

The SDK's internal logs is generated in the /tmp/logs directory by default during runtime:

```
$ ls /tmp/logs/magicbot_z1_sdk.log
/tmp/logs/magicbot_z1_sdk.log
```





---

## Robot Main Control Service (C++)

---

Provides robot system main controller. Through the `MagicRobot` class, you can perform resource initialization, manage communication connections, and access various sub-controllers such as motion controllers, audio, state monitoring, and sensor controllers.

### 7.1 Interface Definition

`MagicRobot` is the unified entry class for the robot SDK.

#### 7.1.1 MagicRobot

Item	Content
Function Name	<code>MagicRobot</code>
Function Declaration	<code>MagicRobot () ;</code>
Function Overview	Constructor, creates <code>MagicRobot</code> instance.
Notes	Constructs internal state.

## 7.1.2 ~MagicRobot

Item	Content
Function Name	<code>~MagicRobot</code>
Function Declaration	<code>~MagicRobot ();</code>
Function Overview	Destructor, releases MagicRobot instance resources.
Notes	Ensures safe resource release.

## 7.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>bool Initialize(const std::string&amp; local_ip);</code>
Function Overview	Initialize robot system, including controllers and network modules.
Parameter Description	<code>local_ip</code> : Local communication IP address.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Must be called before first use.

## 7.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>void Shutdown();</code>
Function Overview	Shutdown robot system and release resources.
Notes	Used in conjunction with Initialize.

## 7.1.5 Release

Item	Content
Function Name	<code>Release</code>
Function Declaration	<code>void Release();</code>
Function Overview	Release resources.
Notes	Releases SDK-occupied topic resources.

### 7.1.6 Connect

Item	Content
Function Name	Connect
Function Declaration	<code>Status Connect();</code>
Function Overview	Establish communication connection with robot service.
Return Value	<code>Status::OK</code> indicates success.
Notes	Blocking interface, must be called after initialization.

### 7.1.7 Disconnect

Item	Content
Function Name	Disconnect
Function Declaration	<code>Status Disconnect();</code>
Function Overview	Disconnect from robot service.
Return Value	gRPC call status.
Notes	Blocking interface, used in conjunction with Connect.

### 7.1.8 GetSDKVersion

Item	Content
Function Name	GetSDKVersion
Function Declaration	<code>std::string GetSDKVersion() const;</code>
Function Overview	Get current SDK version number.
Return Value	SDK version string (e.g., 0.0.1).
Notes	Non-blocking interface, convenient for debugging or log marking.

### 7.1.9 GetMotionControlLevel

Item	Content
Function Name	GetMotionControlLevel
Function Declaration	<code>ControllerLevel GetMotionControlLevel();</code>
Function Overview	Get current motion control level (high-level/low-level).
Return Value	<code>ControllerLevel</code> enumeration value.
Notes	Non-blocking interface, used to determine current control permissions.

### 7.1.10 SetMotionControlLevel

Item	Content
Function Name	SetMotionControlLevel
Function Declaration	<code>Status SetMotionControlLevel(ControllerLevel level);</code>
Function Overview	Set current motion control level.
Parameter Description	level: Control permission enumeration value.
Return Value	Status::OK indicates successful setting, others indicate setting failure.
Notes	Blocking interface, used when switching control modes.

### 7.1.11 GetHighLevelMotionController

Item	Content
Function Name	GetHighLevelMotionController
Function Declaration	<code>HighLevelMotionController&amp; GetHighLevelMotionController();</code>
Function Overview	Get high-level motion controller object.
Return Value	Reference type, used to call high-level control interfaces.
Notes	Non-blocking interface, encapsulates gait, tricks, remote control, etc.

### 7.1.12 GetLowLevelMotionController

Item	Content
Function Name	GetLowLevelMotionController
Function Declaration	<code>LowLevelMotionController&amp; GetLowLevelMotionController();</code>
Function Overview	Get low-level motion controller object.
Return Value	Reference type, used to control joints or motors.
Notes	Non-blocking interface, directly controls joint motors, gets IMU data, etc.

### 7.1.13 GetAudioController

Item	Content
Function Name	GetAudioController
Function Declaration	<code>AudioController&amp; GetAudioController();</code>
Function Overview	Get audio controller object.
Return Value	Reference type, used for audio control.
Notes	Non-blocking interface, plays audio and controls volume.

### 7.1.14 GetSensorController

Item	Content
Function Name	GetSensorController
Function Declaration	<code>SensorController&amp; GetSensorController();</code>
Function Overview	Get sensor controller object.
Return Value	Reference type, used to access sensor data.
Notes	Non-blocking interface, encapsulates LiDAR, RGBD, etc. reading.

### 7.1.15 GetStateMonitor

Item	Content
Function Name	GetStateMonitor
Function Declaration	<code>StateMonitor&amp; GetStateMonitor();</code>
Function Overview	Get state monitor object.
Return Value	Reference type, used to get current robot state information.
Notes	Non-blocking interface, encapsulates reading of BMS, faults, and other state information.

### 7.1.16 GetSlamNavController

Item	Content
Function Name	GetSlamNavController
Function Declaration	<code>SlamNavController&amp; GetSlamNavController();</code>
Function Overview	Get SLAM and navigation controller object.
Return Value	Reference type, used for mapping and localization.
Notes	Non-blocking interface, used for robot SLAM mapping and autonomous navigation functions.



---

## High-Level Motion Control Service (C++)

---

---

Provides robot system high-level motion control service. Through the `HighLevelMotionController`, you can control robot gait, tricks, and remote control via RPC communication.

### 8.1 Interface Definition

`HighLevelMotionController` is a high-level motion controller for semantic control, supporting control operations such as walking, tricks, head movement, etc., encapsulating low-level details for upper system calls.

#### 8.1.1 HighLevelMotionController

Item	Content
Function Name	<code>HighLevelMotionController</code>
Function Declaration	<code>HighLevelMotionController();</code>
Function Overview	Constructor, initializes high-level controller state
Notes	Constructs internal control resources

## 8.1.2 ~HighLevelMotionController

Item	Content
Function Name	<code>~HighLevelMotionController</code>
Function Declaration	<code>virtual ~HighLevelMotionController();</code>
Function Overview	Destructor, releases controller resources
Notes	Used in conjunction with constructor

## 8.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>virtual bool Initialize() override;</code>
Function Overview	Initialize controller, prepare high-level control functions
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure
Notes	Must be called before first use

## 8.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>virtual void Shutdown() override;</code>
Function Overview	Shutdown controller and release resources
Notes	Used in conjunction with <code>Initialize</code> , safely disconnect

## 8.1.5 SetGait

Item	Content
Function Name	<code>SetGait</code>
Function Declaration	<code>Status SetGait(const GaitMode gait_mode, int timeout_ms);</code>
Function Overview	Set robot gait mode (such as recovery stand, balance stand, humanoid walk, etc.)
Parameter Description	<code>gait_mode</code> : Gait control enumeration
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Notes	Blocking interface, can switch between multiple gait modes



### 8.1.6 GetGait

Item	Content
Function Name	GetGait
Function Declaration	<code>Status GetGait(GaitMode&amp; gait_mode);</code>
Function Overview	Get robot gait mode (such as recovery stand, balance stand, humanoid walk, etc.)
Parameter Description	<code>gait_mode</code> : Gait control enumeration
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Notes	Blocking interface, gets current gait mode

### 8.1.7 ExecuteTrick

Item	Content
Function Name	ExecuteTrick
Function Declaration	<code>Status ExecuteTrick(const TrickAction trick_action, int timeout_ms);</code>
Function Overview	Execute trick actions (such as welcome, etc.)
Parameter Description	<code>trick_action</code> : Trick action identifier
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Notes	Blocking interface, ensure robot can currently execute tricks Note: Trick actions must be performed in <code>GaitMode::GAIT_BALANCE_STAND(46)</code> gait

- Note: Trick actions must be performed in `GaitMode::GAIT_BALANCE_STAND(46)` gait to execute trick demonstrations

### 8.1.8 SendJoyStickCommand

Item	Content
Function Name	SendJoyStickCommand
Function Declaration	<code>Status SendJoyStickCommand(const JoystickCommand&amp; joy_command);</code>
Function Overview	Send real-time joystick control commands
Parameter Description	<code>joy_command</code> : Control data containing joystick coordinates
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Notes	Non-blocking interface, recommended sending frequency is 20Hz

### 8.1.9 HeadMove

Item	Content
Function Name	HeadMove
Function Declaration	Status HeadMove(float shake_angle, int timeout_ms);
Function Overview	Control robot head swinging motion
Parameter Description	shake_angle: Head swing angle, unit: rad, range: [-0.698, 0.698] timeout_ms: Timeout duration, default 5000 milliseconds
Return Value	Status::OK indicates success, others indicate failure
Notes	Blocking interface, controls robot head left-right swinging motion

## 8.2 Type Definitions

### 8.2.1 JoystickCommand —High-Level Motion Control Joystick Command Structure

Field Name	Type	Description
left_x_axis	float	Left joystick X-axis direction value (-1.0: left, 1.0: right)
left_y_axis	float	Left joystick Y-axis direction value (-1.0: down, 1.0: up)
right_x_axis	float	Right joystick X-axis direction value (rotation -1.0: left, 1.0: right)
right_y_axis	float	Right joystick Y-axis direction value (purpose not yet defined)

## 8.3 Enumeration Type Definitions


### 8.3.1 GaitMode —Robot Gait Mode Enumeration

Enumeration Value	Value	Description
GAIT_PASSIVE	0	Passive
GAIT_RECOVERY_STAND	1	Recovery Stand
GAIT_BALANCE_STAND	46	Balance Stand (supports movement)
GAIT_HUMANOID_WALK	79	Humanoid Walk
GAIT_LOWLEVEL_SDK	200	Low-Level Control SDK Mode

### 8.3.2 TrickAction —Trick Action Command Enumeration


Enumeration Value	Value	Description
ACTION_SHAKE_LEFT_HAND_REACHOUT	215	Handshake (Left Hand) - Reach Out
ACTION_SHAKE_LEFT_HAND_WITHDRAW	216	Handshake (Left Hand) - Withdraw
ACTION_SHAKE_RIGHT_HAND_REACHOUT	217	Handshake (Right Hand) - Reach Out
ACTION_SHAKE_RIGHT_HAND_WITHDRAW	218	Handshake (Right Hand) - Withdraw
ACTION_SHAKE_HEAD	220	Shake Head
ACTION_LEFT_GREETING	300	Greeting (Left Hand)
ACTION_RIGHT_GREETING	301	Greeting (Right Hand)
ACTION_TRUN_LEFT_INTRODUCE_HIGH	304	Turn Left Introduce - High
ACTION_TRUN_LEFT_INTRODUCE_LOW	305	Turn Left Introduce - Low
ACTION_TRUN_RIGHT_INTRODUCE_HIGH	306	Turn Right Introduce - High
ACTION_TRUN_RIGHT_INTRODUCE_LOW	307	Turn Right Introduce - Low
ACTION_WELCOME	340	Welcome
FLY_KISS_LEFT	408	Air Kiss - Left Hand
FLY_KISS_RIGHT	409	Air Kiss - Right Hand
SUPERMAN_WAVE	410	Superman Wave
CLAP_HAND	411	Clap Hands
HOLD_CERT_REACHOUT	412	Hold Certificate - Reach Out
HOLD_CERT_WITHDRAW	413	Hold Certificate - Withdraw
HUG_REACHOUT	414	Hug with Both Hands - Reach Out
HUG_WITHDRAW	415	Hug with Both Hands - Withdraw
TRUN_WAVE_LEFT	417	Turn and Wave - Left Hand
TRUN_WAVE_RIGHT	418	Turn and Wave - Right Hand
RIGHT_HAND_SALUTE	419	Right Hand Salute

## 8.4 Joystick Diagram



1. The X-axis and Y-axis value ranges for left and right joysticks are  $[-1.0, 1.0]$ ;
2. The up/right direction of the left and right joystick X-axis and Y-axis is positive, as shown in the diagram;

## 8.5 Head Movement Range Diagram



- Movement Range  $[-40^\circ, 40^\circ]$  ( $[-0.698\text{rad}, 0.698\text{rad}]$ )

## 8.6 High-Level Motion Control Robot State Introduction


Robot motion includes recovery stand, balance stand, basic motion, and trick action states. During operation, the robot switches between different states through a state machine to achieve different control tasks. The explanations for each state are as follows:

- **Recovery Stand:** Recovery stand is the state connecting robot suspension landing and balance stand. The robot needs to enter the balance stand state before calling corresponding motion services to achieve robot control.
- **Balance Stand:** In the balance stand state, you can call various SDK interfaces to achieve robot trick actions and

basic motion control.

- **Basic Motion:** During motion execution, you can call SDK interfaces to make the robot enter different gaits.
- **Trick Actions:** When entering the special action execution state, other motion control services will be suspended first, waiting for the current action to complete and enter the balance stand state before taking effect again.


Robot state switching mechanism;



## 8.7 High-Level Motion Control Interface

Robot high-level motion control services can be divided into basic motion control and trick action control.

- In basic motion control services, you can call corresponding interfaces to switch robot walking gaits according to different terrain scenarios and task requirements.
- In trick action control services, you can call corresponding interfaces to achieve robot built-in special tricks, such as celebrate, handshake, greeting, etc.



### 8.7.1 Gait Switching

Current Gait	Gait Switching Process	Diagram
Recovery Stand		
Balance Stand		
Arm Swing Walk		
Humanoid Walk		

## 8.7.2 Trick Execution

Trick	Trick Execution Process	Diagram
Welcome		
Shake Head		
Greeting (Left Hand)		
Greeting (Right Hand)		
Handshake (Left Hand)		
Handshake (Right Hand)		
Turn Left Introduction		
Turn Right Introduction		



---

## Low-Level Motion Control Service (C++)

---

---

Provides robot system low-level motion control service. Through the `LowLevelMotionController`, you can control robot joints and obtain status via topic communication.

### 9.1 Interface Definition

`LowLevelMotionController` is a motion controller for low-level development, supporting direct control and state subscription of motion components such as arms, legs, head, waist, hands, etc., as well as body IMU data acquisition.

#### 9.1.1 `LowLevelMotionController`

Item	Content
Function Name	<code>LowLevelMotionController</code>
Function Declaration	<code>LowLevelMotionController();</code>
Function Overview	Constructor, initializes low-level controller object.
Notes	Constructs internal resources.

## 9.1.2 ~LowLevelMotionController

Item	Content
Function Name	<code>~LowLevelMotionController</code>
Function Declaration	<code>virtual ~LowLevelMotionController();</code>
Function Overview	Destructor, releases resources.
Notes	Cleans up low-level resources.

## 9.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>virtual bool Initialize() override;</code>
Function Overview	Initialize controller, establish low-level connections.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Must be initialized on first call.

## 9.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>virtual void Shutdown() override;</code>
Function Overview	Shutdown controller, release low-level resources.
Notes	Used in conjunction with <code>Initialize</code> .

## 9.1.5 SubscribeArmState

Item	Content
Function Name	<code>SubscribeArmState</code>
Function Declaration	<code>void SubscribeArmState(ArmJointStateCallback callback);</code>
Function Overview	Subscribe to arm joint state data
Parameter Description	<code>callback</code> : Data processing function
Notes	Non-blocking interface.

### 9.1.6 PublishArmCommand

Item	Content
Function Name	PublishArmCommand
Function Declaration	<code>Status PublishArmCommand(const JointCommand&amp; command);</code>
Function Overview	Publish arm control commands
Parameter Description	command: Target position/velocity etc.
Return Value	true indicates success, false indicates failure.
Notes	Non-blocking interface.

### 9.1.7 SubscribeLegState

Item	Content
Function Name	SubscribeLegState
Function Declaration	<code>void SubscribeLegState(LegJointStateCallback callback);</code>
Function Overview	Subscribe to leg joint state data
Parameter Description	callback: Data processing function
Notes	Non-blocking interface.

### 9.1.8 PublishLegCommand

Item	Content
Function Name	PublishLegCommand
Function Declaration	<code>Status PublishLegCommand(const JointCommand&amp; command);</code>
Function Overview	Publish leg control commands
Parameter Description	command: Target position/velocity etc.
Return Value	true indicates success, false indicates failure.
Notes	Non-blocking interface, called when publishing or subscribing.

### 9.1.9 SubscribeHeadState

Item	Content
Function Name	SubscribeHeadState
Function Declaration	<code>void SubscribeHeadState(HeadJointStateCallback callback);</code>
Function Overview	Subscribe to head joint state data
Parameter Description	callback: Data processing function
Notes	Non-blocking interface.

### 9.1.10 PublishHeadCommand

Item	Content
Function Name	PublishHeadCommand
Function Declaration	<code>Status PublishHeadCommand(const JointCommand&amp; command);</code>
Function Overview	Publish head control commands
Parameter Description	command: Target position/velocity etc.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Non-blocking interface.

### 9.1.11 SubscribeWaistState

Item	Content
Function Name	SubscribeWaistState
Function Declaration	<code>void SubscribeWaistState(WaistJointStateCallback callback);</code>
Function Overview	Subscribe to waist joint state data
Parameter Description	callback: Data processing function
Notes	Non-blocking interface.

### 9.1.12 PublishWaistCommand

Item	Content
Function Name	PublishWaistCommand
Function Declaration	<code>Status PublishWaistCommand(const JointCommand&amp; command);</code>
Function Overview	Publish waist control commands
Parameter Description	command: Target position/velocity etc.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Non-blocking interface.

### 9.1.13 SubscribeHandState

Item	Content
Function Name	SubscribeHandState
Function Declaration	<code>void SubscribeHandState(HandStateCallback callback);</code>
Function Overview	Subscribe to hand state data
Parameter Description	callback: Data processing function
Notes	Non-blocking interface.

### 9.1.14 PublishHandCommand

Item	Content
Function Name	PublishHandCommand
Function Declaration	<code>Status PublishHandCommand(const HandCommand&amp; command);</code>
Function Overview	Publish hand control commands
Parameter Description	command: Hand joint target position etc.
Return Value	true indicates success, false indicates failure.
Notes	Non-blocking interface.

### 9.1.15 SubscribeBodyImu

Item	Content
Function Name	SubscribeBodyImu
Function Declaration	<code>void SubscribeBodyImu(const BodyImuCallback&amp; callback);</code>
Function Overview	Subscribe to body IMU data
Parameter Description	callback: IMU data processing function
Notes	Non-blocking interface.

### 9.1.16 SubscribeEstimatorState

Item	Content
Function Name	SubscribeEstimatorState
Function Declaration	<code>void SubscribeEstimatorState(const EstimatorStateCallback&amp; callback);</code>
Function Overview	Subscribe to estimator state data
Parameter Description	callback: estimator state data processing function
Notes	Non-blocking interface.

### 9.1.17 UnsubscribeArmState

Item	Content
Function Name	UnsubscribeArmState
Function Declaration	<code>void UnsubscribeArmState();</code>
Function Overview	Unsubscribe from arm joint state data
Notes	Non-blocking interface, used in conjunction with SubscribeArmState.

### 9.1.18 UnsubscribeLegState

Item	Content
Function Name	UnsubscribeLegState
Function Declaration	<code>void UnsubscribeLegState();</code>
Function Overview	Unsubscribe from leg joint state data
Notes	Non-blocking interface, used in conjunction with SubscribeLegState.

### 9.1.19 UnsubscribeHeadState

Item	Content
Function Name	UnsubscribeHeadState
Function Declaration	<code>void UnsubscribeHeadState();</code>
Function Overview	Unsubscribe from head joint state data
Notes	Non-blocking interface, used in conjunction with SubscribeHeadState.

### 9.1.20 UnsubscribeWaistState

Item	Content
Function Name	UnsubscribeWaistState
Function Declaration	<code>void UnsubscribeWaistState();</code>
Function Overview	Unsubscribe from waist joint state data
Notes	Non-blocking interface, used in conjunction with SubscribeWaistState.

### 9.1.21 UnsubscribeHandState

Item	Content
Function Name	UnsubscribeHandState
Function Declaration	<code>void UnsubscribeHandState();</code>
Function Overview	Unsubscribe from hand state data
Notes	Non-blocking interface, used in conjunction with SubscribeHandState.

### 9.1.22 UnsubscribeBodyImu

Item	Content
Function Name	UnsubscribeBodyImu
Function Declaration	<code>void UnsubscribeBodyImu();</code>
Function Overview	Unsubscribe from body IMU data
Notes	Non-blocking interface, used in conjunction with SubscribeBodyImu.

### 9.1.23 UnsubscribeEstimatorState

Item	Content
Function Name	UnsubscribeEstimatorState
Function Declaration	<code>void UnsubscribeEstimatorState();</code>
Function Overview	Unsubscribe from body state estimator data
Notes	Non-blocking interface, used in conjunction with SubscribeEstimatorState.

## 9.2 Type Definitions

### 9.2.1 SingleHandJointCommand —Single Hand Joint Control Command

Field Name	Type	Description
<code>operation_mode</code>	<code>int16_t</code>	Control word
<code>pos</code>	<code>vector&lt;float&gt;;</code>	Desired position array (7 DOF, unit: rad)

### 9.2.2 HandCommand —Complete Hand Control Command

Field Name	Type	Description
<code>timestamp</code>	<code>int64_t</code>	Timestamp (unit: nanoseconds)
<code>cmd</code>	<code>vector&lt;SingleHandJointCommand&gt;;</code>	Control command array, left hand and right hand in order

### 9.2.3 SingleHandJointState —Single Hand Joint State

Field Name	Type	Description
status_word	int16_t	Status word
pos	vector<float>;	Current position (unit: rad)
toq	vector<float>;	Current torque (unit: Nm)
cur	vector<float>;	Current current (unit: A)
error_code	int16_t	Error code

### 9.2.4 HandState —Complete Hand State Information

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
state	vector<SingleHandJointState>;	All hand joint states (left hand, right hand order)

### 9.2.5 SingleJointCommand —Single Joint Control Command

Field Name	Type	Description
operation_mode	int16_t	Control mode identifier: • 200 = Standby mode • 3 = Parallel triple-loop control (MIT mode) • 4 = Serial triple-loop control
pos	float	Target position (unit: rad)
vel	float	Velocity limit (unit: rad/s)
toq	float	Torque limit (unit: Nm)
kp	float	Position loop proportional gain
kd	float	Velocity loop derivative gain

- For joints 1-5 of the arm, the `operation_mode` needs to be switched from mode 200 (standby) to mode 3 (parallel triple-loop control, MIT mode) before sending commands.
- For joint 1 of the waist, the `operation_mode` needs to be switched from mode 200 (standby) to mode 3 (parallel triple-loop control, MIT mode) before sending commands.
- For joints 1-6 of the legs, the `operation_mode` needs to be switched from mode 200 (standby) to mode 3 (parallel triple-loop control, MIT mode) before sending commands.
- The head joint uses pure position control and does not require setting `operation_mode`.



## 9.2.6 JointCommand —Joint Control Command

Lower limbs contain 12 joint items, upper limbs 10(14), head 1(2), waist 1:

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
joints	vector<SingleJointCommand>	Control commands for all joints

## 9.2.7 SingleJointState —Single Joint State Information

Field Name	Type	Description
status_word	int16_t	Current joint state (custom state machine encoding)
posH	float	Actual position (high-precision encoder reading)
posL	float	Actual position (low-precision encoder reading, for redundancy check)
vel	float	Current velocity (unit: rad/s or m/s, automatically switches based on joint type)
toq	float	Current torque (unit: Nm)
current	float	Current current (unit: A)
err_code	int16_t	Error code (such as encoder exception, motor overcurrent, etc., see error code reference table)

## 9.2.8 JointState —Joint State Data

Lower limbs contain 12 joint items, upper limbs 10(14), head 1(2), waist 1:

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
joints	vector<SingleJointState>	State data for all joints

## 9.2.9 EstimatorState —State Estimation Data

Field Name	Type	Description
w_base_pos	std::array<double, 3>	Robot base position(m) in world coordinates
w_com_pos	std::array<double, 3>	Center of mass position(m) in world coordinates
w_com_vel	std::array<double, 3>	Center of mass velocity(m/s) in world coordinates
w_base_vel	std::array<double, 3>	Robot base velocity(m/s) in world coordinates
b_base_vel	std::array<double, 3>	Robot base velocity(m/s) in body coordinates

## 9.2.10 Joint Motor Order

### Head Joint

Index	Joint Name
0	head_joint

### Arm Joints

Index	Joint Name
0	left_shoulder_pitch_joint
1	left_shoulder_roll_joint
2	left_shoulder_yaw_joint
3	left_elbow_joint
4	left_wrist_yaw_joint
5	left_wrist_roll_joint
6	left_wrist_pitch_joint
7	right_shoulder_pitch_joint
8	right_shoulder_roll_joint
9	right_shoulder_yaw_joint
10	right_elbow_roll_joint
11	right_wrist_yaw_joint
12	right_wrist_roll_joint
13	right_wrist_pitch_joint

### Waist Joint

Index	Joint Name
0	waist_yaw_joint

## Leg Joints


Index	Joint Name
0	left_hip_pitch_joint
1	left_hip_roll_joint
2	left_hip_yaw_joint
3	left_knee_joint
4	left_ankle_pitch_joint
5	left_ankle_roll_joint
6	right_hip_pitch_joint
7	right_hip_roll_joint
8	right_hip_yaw_joint
9	right_knee_joint
10	right_ankle_pitch_joint
11	right_ankle_roll_joint

## 9.3 URDF Reference

Robot URDF

## 9.4 Low-Level Motion Control Robot State Introduction

Robot low-level motion mainly develops three-loop control of joints for developers to perform secondary development of robot motion capabilities, basic control state switching mechanism:



## 9.5 Notice:

- When using subscription-type SDK interfaces such as `Subscribe`, do not perform blocking operations within the callback function. Doing so may cause message congestion, processing delays, or even unexpected errors.
- The Z1 robot's upper arm joints have 5-degree-of-freedom and 7-degree-of-freedom SKU versions. For different versions, the joint motor sequence and names are used in order, and nonexistent joints can be ignored.

---

## Sensor Control Service (C++)

---

---

Provides robot system sensor (LiDAR/RGBD camera/binocular camera) services. Through the `SensorController`, you can control robot sensors and obtain status via RPC and topic methods.

### 10.1 Interface Definition

`SensorController` is a management class that encapsulates various robot sensors, supporting initialization, control, and data subscription of LiDAR, RGBD cameras, and binocular cameras.

#### 10.1.1 `SensorController`

Item	Content
Function Name	<code>SensorController</code>
Function Declaration	<code>SensorController();</code>
Function Overview	Constructor, initializes sensor controller object.
Notes	Constructs internal state.

### 10.1.2 ~SensorController

Item	Content
Function Name	<code>~SensorController</code>
Function Declaration	<code>virtual ~SensorController();</code>
Function Overview	Destructor, releases all sensor resources.
Notes	Sensors should be closed before calling.

### 10.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>bool Initialize();</code>
Function Overview	Initialize controller, including resource allocation and driver loading.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Object must be constructed before calling.

### 10.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>void Shutdown();</code>
Function Overview	Close all sensor connections and release resources.
Notes	Used in conjunction with <code>Initialize</code> .

### 10.1.5 OpenLidar

Item	Content
Function Name	<code>OpenLidar</code>
Function Declaration	<code>Status OpenLidar();</code>
Function Overview	Open LiDAR.
Return Value	<code>Status::OK</code> indicates success, others indicate failure.
Notes	Blocking interface.

## 10.1.6 CloseLidar

Item	Content
Function Name	CloseLidar
Function Declaration	<code>Status CloseLidar();</code>
Function Overview	Close LiDAR.
Return Value	<code>Status::OK</code> indicates success, others indicate failure.
Notes	Blocking interface, used in conjunction with open function.

## 10.1.7 OpenRgbCamera

Item	Content
Function Name	OpenRgbCamera
Function Declaration	<code>Status OpenRgbCamera();</code>
Function Overview	Open RGBD camera (head).
Return Value	<code>Status::OK</code> indicates success, others indicate failure.
Notes	Blocking interface.

## 10.1.8 CloseRgbCamera

Item	Content
Function Name	CloseRgbCamera
Function Declaration	<code>Status CloseRgbCamera();</code>
Function Overview	Close RGBD camera.
Return Value	<code>Status::OK</code> indicates success, others indicate failure.
Notes	Blocking interface, used in conjunction with open function.

## 10.1.9 OpenBinocularCamera

Item	Content
Function Name	OpenBinocularCamera
Function Declaration	<code>Status OpenBinocularCamera();</code>
Function Overview	Open binocular camera.
Return Value	<code>Status::OK</code> indicates success, others indicate failure.
Notes	Blocking interface.

### 10.1.10 CloseBinocularCamera

Item	Content
Function Name	CloseBinocularCamera
Function Declaration	<code>Status CloseBinocularCamera();</code>
Function Overview	Close binocular camera.
Return Value	Status: :OK indicates success, others indicate failure.
Notes	Blocking interface.

### 10.1.11 SubscribeLidarImu

Item	Content
Function Name	SubscribeLidarImu
Function Declaration	<code>void SubscribeLidarImu(const LidarImuCallback&amp; callback);</code>
Function Overview	Subscribe to LiDAR IMU data
Parameter Description	callback: Data processing function after receiving data
Notes	Non-blocking interface, callback function will be called when data is updated.

### 10.1.12 SubscribeLidarPointCloud

Item	Content
Function Name	SubscribeLidarPointCloud
Function Declaration	<code>void SubscribeLidarPointCloud(const LidarPointCloudCallback&amp; callback);</code>
Function Overview	Subscribe to LiDAR point cloud data
Parameter Description	callback: Point cloud processing function after receiving data
Notes	Non-blocking interface, callback function will be called when data is updated.



### 10.1.13 SubscribeHeadRgbColorImage

Item	Content
Function Name	SubscribeHeadRgbColorImage
Function Declaration	<code>void SubscribeHeadRgbColorImage(const RgbImageCallback&amp; callback);</code>
Function Overview	Subscribe to head RGB color image data
Parameter Description	callback: Image processing function after receiving data
Notes	Non-blocking interface, callback function will be called when data is updated.

### 10.1.14 SubscribeHeadRgbDepthImage

Item	Content
Function Name	SubscribeHeadRgbDepthImage
Function Declaration	<code>void SubscribeHeadRgbDepthImage(const RgbImageCallback&amp; callback);</code>
Function Overview	Subscribe to head RGB depth image data
Parameter Description	callback: Image processing function after receiving data
Notes	Non-blocking interface, callback function will be called when data is updated.

### 10.1.15 SubscribeHeadRgbCameraInfo

Item	Content
Function Name	SubscribeHeadRgbCameraInfo
Function Declaration	<code>void SubscribeHeadRgbCameraInfo(const RgbCameraInfoCallback&amp; callback);</code>
Function Overview	Subscribe to head RGB camera parameters
Parameter Description	callback: Parameter processing function after receiving data
Notes	Non-blocking interface, callback function will be called when data is updated.

### 10.1.16 SubscribeBinocularImage

Item	Content
Function Name	SubscribeBinocularImage
Function Declaration	<code>void SubscribeBinocularImage(const BinocularImageCallback&amp; callback);</code>
Function Overview	Subscribe to binocular camera image frames
Parameter Description	callback: Image frame processing function after receiving data
Notes	Non-blocking interface, callback function will be called when data is updated.

### 10.1.17 SubscribeBinocularCameraInfo

Item	Content
Function Name	SubscribeBinocularCameraInfo
Function Declaration	<code>void SubscribeBinocularCameraInfo(const RgbdcameraInfoCallback&amp; callback);</code>
Function Overview	Subscribe to binocular camera parameters
Parameter Description	callback: Parameter processing function after receiving data
Notes	Non-blocking interface, callback function will be called when data is updated.

## 10.2 Type Definitions

### 10.2.1 Imu —IMU Data Structure

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
orientation[4]	std::array<double, 4>;	Attitude quaternion (w, x, y, z)
angular_velocity[3]	std::array<double, 3>;	Angular velocity (unit: rad/s)
linear_acceleration[3]	std::array<double, 3>;	Linear acceleration (unit: m/s <sup>2</sup> )
temperature	float	Temperature (unit: Celsius or other, unit should be specified)

## 10.2.2 Header —Common Message Header Structure

Field Name	Type	Description
stamp	int64_t	Timestamp (unit: nanoseconds)
frame_id	std::string	Coordinate frame name

## 10.2.3 PointField —Point Field Description

Field Name	Type	Description
name	std::string	Field name (such as x, y, z, intensity)
offset	int32_t	Starting byte offset
datatype	int8_t	Data type (corresponding constant)
count	int32_t	Number of elements this field contains per point

## 10.2.4 PointCloud2 —Point Cloud Data Structure

Field Name	Type	Description
header	Header	Message header
height	int32_t	Number of rows
width	int32_t	Number of columns
fields	vector<PointField>	Point field array
is_bigendian	bool	Byte order
point_step	int32_t	Number of bytes per point
row_step	int32_t	Number of bytes per row
data	vector<uint8_t>	Raw point cloud byte data
is_dense	bool	Whether dense point cloud

## 10.2.5 Image —Image Data Structure

Field Name	Type	Description
header	Header	Message header
height	int32_t	Image height (pixels)
width	int32_t	Image width (pixels)
encoding	std::string	Encoding type (such as rgb8, mono8)
is_bigendian	bool	Whether big-endian mode
step	int32_t	Number of bytes per image row
data	vector<uint8_t>	Raw image byte data

## 10.2.6 CameraInfo —Camera Intrinsic Parameters and Distortion Information

Field Name	Type	Description
header	Header	Message header
height	int32_t	Image height
width	int32_t	Image width
distortion_model	std::string	Distortion model (such as plumb_bob)
D	vector<double>;	Distortion parameter array
K	std::array<double, 9>;	Camera intrinsic parameter matrix
R	std::array<double, 9>;	Rectification matrix
P	std::array<double, 12>;	Projection matrix
binning_x	int32_t	Horizontal binning coefficient
binning_y	int32_t	Vertical binning coefficient
roi_x_offset	int32_t	ROI starting x coordinate
roi_y_offset	int32_t	ROI starting y coordinate
roi_height	int32_t	ROI height
roi_width	int32_t	ROI width
roi_do_rectify	bool	Whether to perform rectification

## 10.2.7 BinocularCameraFrame —Binocular Camera Frame Data Structure

Field Name	Type	Description
header	Header	Common message header
format	std::string	Image format
data	vector<uint8_t>;	Left eye and binocular stitched image data, left half is left eye image, right half is right eye image

## 10.3 Notice:

When using subscription-type SDK interfaces such as Subscribe, do not perform blocking operations within the callback function. Doing so may cause message congestion, processing delays, or even unexpected errors.

---

## Audio Control Service (C++)

---

---

Provides robot system audio service controller. Through the `AudioController`, you can control robot audio and obtain status via RPC methods.

### 11.1 Interface Definition

`AudioController` is a C++ class that encapsulates audio control functionality, mainly used for audio playback control, TTS playback, volume setting and query, etc.

#### 11.1.1 `AudioController`

Item	Content
Function Name	<code>AudioController</code>
Function Declaration	<code>AudioController() ;</code>
Function Overview	Initialize audio controller object, construct internal state, allocate resources, etc.
Notes	Constructs internal state.

### 11.1.2 ~AudioController

Item	Content
Function Name	<code>~AudioController</code>
Function Declaration	<code>~AudioController();</code>
Function Overview	Release audio controller resources, ensure playback stops and clean up low-level resources.
Notes	Ensures safe resource release.

### 11.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>bool Initialize();</code>
Function Overview	Initialize audio control module, prepare playback resources and devices.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Used in conjunction with <code>Shutdown()</code> .

### 11.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>void Shutdown();</code>
Function Overview	Shutdown audio controller and release resources.
Notes	Ensure called before destruction.

### 11.1.5 Play

Item	Content
Function Name	<code>Play</code>
Function Declaration	<code>Status Play(const TtsCommand&amp; cmd, int timeout_ms);</code>
Function Overview	Play TTS (text-to-speech) voice commands.
Parameter Description	<code>cmd</code> : TTS command, contains text, speech rate, tone, etc.
Return Value	<code>Status::OK</code> indicates success, others indicate failure state.
Notes	Blocking interface, ensure module is initialized before calling.

### 11.1.6 Stop

Item	Content
Function Name	Stop
Function Declaration	<code>Status Stop();</code>
Function Overview	Stop current audio playback.
Return Value	<code>Status::OK</code> indicates success, others indicate failure state.
Notes	Blocking interface, usually used to interrupt current voice.

### 11.1.7 SetVolume

Item	Content
Function Name	SetVolume
Function Declaration	<code>Status SetVolume(int volume);</code>
Function Overview	Set audio output volume.
Parameter Description	<code>volume</code> : Volume value, typically ranges from 0~100.
Return Value	<code>Status::OK</code> indicates success, others indicate failure state.
Notes	Blocking interface, takes effect immediately after setting.

### 11.1.8 GetVolume

Item	Content
Function Name	GetVolume
Function Declaration	<code>Status GetVolume(int&amp; volume);</code>
Function Overview	Get current audio output volume.
Parameter Description	<code>volume</code> : Returns current volume value by reference.
Return Value	<code>Status::OK</code> indicates success, others indicate failure state.
Notes	Blocking interface, return value should be checked before using <code>volume</code> .

### 11.1.9 OpenAudioStream

Item	Content
Function Name	OpenAudioStream
Function Declaration	<code>Status OpenAudioStream();</code>
Function Overview	Open audio stream, prepare for audio playback.
Return Value	Operation status, returns <code>Status::OK</code> on success.

### 11.1.10 CloseAudioStream

Item	Content
Function Name	CloseAudioStream
Function Declaration	<code>Status CloseAudioStream();</code>
Function Overview	Close audio stream.
Return Value	Operation status, returns Status::OK on success.

### 11.1.11 SubscribeOriginAudioStream

Item	Content
Function Name	SubscribeOriginAudioStream
Function Declaration	<code>void SubscribeOriginAudioStream(const OriginAudioStreamCallback callback);</code>
Function Overview	Subscribe to original audio stream data.
Parameter Description	callback: Processing callback function after receiving original audio stream data

### 11.1.12 UnsubscribeOriginAudioStream

Item	Content
Function Name	UnsubscribeOriginAudioStream
Function Declaration	<code>void UnsubscribeOriginAudioStream();</code>
Function Overview	Unsubscribe from original audio stream data.

### 11.1.13 SubscribeBfAudioStream

Item	Content
Function Name	SubscribeBfAudioStream
Function Declaration	<code>void SubscribeBfAudioStream(const BfAudioStreamCallback callback);</code>
Function Overview	Subscribe to BF audio stream data.
Parameter Description	callback: Processing callback function after receiving BF audio stream data



### 11.1.14 UnsubscribeBfAudioStream

Item	Content
Function Name	UnsubscribeBfAudioStream
Function Declaration	<code>void UnsubscribeBfAudioStream();</code>
Function Overview	Unsubscribe from BF audio stream data.

### 11.1.15 OpenWakeupStatusStream

Item	Content
Function Name	OpenWakeupStatusStream
Function Declaration	<code>Status OpenWakeupStatusStream();</code>
Function Overview	Enable voice wakeup status stream.
Return Value	Operation status, returns Status::OK on success.

### 11.1.16 CloseWakeupStatusStream

Item	Content
Function Name	CloseWakeupStatusStream
Function Declaration	<code>Status CloseWakeupStatusStream();</code>
Function Overview	Disable voice wakeup status stream.
Return Value	Operation status, returns Status::OK on success.

### 11.1.17 SubscribeWakeupStatus

Item	Content
Function Name	SubscribeWakeupStatus
Function Declaration	<code>void SubscribeWakeupStatus(const WakeupStatusCallback callback);</code>
Function Overview	Subscribe to voice wakeup status.
Parameter Description	callback: Processing callback function after receiving wakeup status

### 11.1.18 UnsubscribeWakeupStatus

Item	Content
Function Name	UnsubscribeWakeupStatus
Function Declaration	<code>void UnsubscribeWakeupStatus();</code>
Function Overview	Unsubscribe from voice wakeup status.

## 11.2 Type Definitions

### 11.2.1 TtsPriority —TTS Playback Priority Level

Used to control interrupt behavior between different TTS tasks. Higher priority tasks will interrupt playback of current lower priority tasks.

Enumeration Value	Description
<code>TtsPriority::HIGH</code>	Highest priority, e.g.: low battery warning, emergency alerts
<code>TtsPriority::MIDDLE</code>	Medium priority, e.g.: system prompts, status announcements
<code>TtsPriority::LOW</code>	Lowest priority, e.g.: daily voice conversation, background announcements

### 11.2.2 TtsMode —Task Scheduling Strategy Under Same Priority

Used to fine-tune control of playback order and clearing logic for multiple TTS tasks under the same priority conditions.

Enumeration Value	Description
<code>TtsMode::CLEARTOP</code>	Clear all tasks of current priority (including currently playing and waiting queue), immediately play this request
<code>TtsMode::ADD</code>	Append this request to the end of current priority queue, play in order (does not interrupt current playback)
<code>TtsMode::CLEARBUFF</code>	Clear unplayed requests in queue, keep current playback, then play this request

## 11.3 Structure Definitions

### 11.3.1 TtsCommand —TTS Playback Command Structure

Describes complete information for a TTS playback request, supporting unique identifier, text content, priority control, and scheduling mode under same priority.


Field Name	Type	Description
id	std::string	TTS task unique ID, e.g. "id_01", used to track playback status
content	std::string	Text content to be played, e.g. "Hello, welcome to the intelligent voice system."
priority	TtsPriority	Playback priority, controls whether to interrupt currently playing low-priority voice
mode	TtsMode	Scheduling strategy under same priority, controls whether tasks are appended, overridden, etc.

### 11.3.2 `AudioStream` - Audio Stream Structure

Describes raw audio stream or BF audio stream data.

Field Name	Type	Description
data_length	int32_t	Data length
raw_data	std::vector<uint8_t>	Audio stream data

## 11.4 DOA



## 11.5 Notice:

When using subscription-type SDK interfaces such as `Subscribe`, do not perform blocking operations within the callback function. Doing so may cause message congestion, processing delays, or even unexpected errors.

---

## State Monitor Service (C++)

---

---

Provides robot state monitoring interface class. Through the `StateMonitor`, you can provide state query and other interfaces.

### 12.1 Interface Definition

`StateMonitor` is a robot system state monitoring management class, typically used to control robot state management, supporting state queries.

#### 12.1.1 `StateMonitor`

Item	Content
Function Name	<code>StateMonitor</code>
Function Declaration	<code>StateMonitor();</code>
Function Overview	Constructor, initializes state monitor object.
Notes	Constructs internal state.

## 12.1.2 ~StateMonitor

Item	Content
Function Name	<code>~StateMonitor</code>
Function Declaration	<code>virtual ~StateMonitor();</code>
Function Overview	Destructor, releases resources.
Notes	Sensors should be closed before calling.

## 12.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>bool Initialize();</code>
Function Overview	Initialize controller, including resource allocation and driver loading.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Object must be constructed before calling.

## 12.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>void Shutdown();</code>
Function Overview	Shutdown and release resources.
Notes	Used in conjunction with <code>Initialize</code> .

## 12.1.5 GetCurrentState

Item	Content
Function Name	<code>GetCurrentState</code>
Function Declaration	<code>RobotState GetCurrentState();</code>
Function Overview	Get current robot aggregated state
Return Value	<code>Status::OK</code> indicates success, others indicate failure.
Notes	Non-blocking interface, gets recently monitored robot state data, including BMS/fault state monitoring, etc., will be iteratively expanded

### 12.1.6 RobotState —Robot State Data Structure

Used to represent overall robot state information:

Field Name	Type	Description
faults	vector<Fault>;	Fault information list
bms_data	BmsData	Battery management system data

### 12.1.7 BmsData —Battery Management System Data Structure

Represents battery state information:

Field Name	Type	Description
battery_percentage	float	Current battery remaining power (percentage, 0~100)
battery_health	float	Battery health status (higher is better)
battery_state	BatteryState	Battery state (see enumeration below)
power_supply_status	PowerSupplyStatus	Battery charge/discharge state (see enumeration below)

### 12.1.8 Enumeration Type Definitions

#### BatteryState —Battery State Enumeration Type

Used to represent current battery state, for battery state judgment and processing in the system:

Enumeration Value	Value	Description
BatteryState::UNKNOWN	0	Unknown state
BatteryState::GOOD	1	Battery state good
BatteryState::OVERHEAT	2	Battery overheating
BatteryState::DEAD	3	Battery damaged
BatteryState::OVERVOLTAGE	4	Battery overvoltage
BatteryState::UNSPEC_FAILURE	5	Unknown fault
BatteryState::COLD	6	Battery too cold
BatteryState::WATCHDOG_TIMER_EXPIRE	7	Watchdog timer timeout
BatteryState::SAFETY_TIMER_EXPIRE	8	Safety timer timeout

#### PowerSupplyStatus —Battery Charge/Discharge State

Used to represent current battery charge/discharge state:

Enumeration Value	Value	Description
PowerSupplyStatus::UNKNOWN	0	Unknown state
PowerSupplyStatus::CHARGING	1	Battery charging
PowerSupplyStatus::DISCHARGING	2	Battery discharging
PowerSupplyStatus::NOTCHARGING	3	Battery not charging/discharging
PowerSupplyStatus::FULL	4	Battery fully charged

## 12.2 Error Code Mapping Table

Error Code (Hexadecimal)	Error Description
0x0000	No fault
0x1101	Service invocation failed
0x1301	Central control node lost
0x1302	App node lost
0x1303	Audio node lost
0x1304	Stereo camera node lost
0x1305	LIDAR node lost
0x1306	SLAM node lost
0x1307	Navigation node lost
0x1308	AI node lost
0x1309	Head node lost
0x130A	Point cloud node lost
0x2201	No LIDAR data received
0x2202	No stereo camera data received
0x2203	Stereo camera data error
0x2204	Stereo camera initialization failed
0x220B	No odometry data received
0x220C	No IMU data received
0x2215	Depth camera not detected
0x3101	Failed to connect robot to app
0x3102	Heartbeat lost - assertion failed
0x4201	Failed to open head serial port
0x4202	No head data received
0x5201	No navigation TF data
0x5202	No navigation map data
0x5203	No navigation localization data
0x5204	No navigation LIDAR data

continues on next page



Table 1 – continued from previous page

Error Code (Hexadecimal)	Error Description
0x5205	No navigation depth camera data
0x5206	No navigation multi-line LIDAR data
0x5207	No navigation odometry data
0x6201	SLAM localization error
0x6102	No SLAM LIDAR data
0x6103	No SLAM odometry data
0x6104	SLAM map data error
0x7201	LCM connection timeout
0x8201	Left leg hardware error
0x8202	Right leg hardware error
0x8203	Left arm hardware error
0x8204	Right arm hardware error
0x8205	Waist hardware error
0x8206	Head hardware error
0x8207	Hand hardware error
0x8208	Gripper hardware error
0x8209	IMU hardware error
0x820A	Power system hardware error
0x820B	Leg force sensor hardware error
0x820C	Arm force sensor hardware error
0x9201	ECAT (EtherCAT) hardware error
0xA201	Motion posture error
0xA202	Foot position deviation during movement
0xA203	Joint velocity error during motion



---

## SLAM Navigation Control Service (C++)

---

---

Provides SLAM (Simultaneous Localization and Mapping) and navigation control services for robot systems. Through `SlamNavController`, RPC communication can be used to control robot mapping, localization, navigation and other functions.

### 13.1 Interface Definition

`SlamNavController` is a controller for SLAM and navigation control, supporting control operations such as mapping, localization, navigation, and map management, encapsulating underlying details for upper-level system calls.

#### 13.1.1 `SlamNavController`

Item	Content
Function Name	<code>SlamNavController</code>
Function Declaration	<code>SlamNavController();</code>
Function Overview	Constructor, initializes SLAM navigation controller state
Remarks	Constructs internal control resources

### 13.1.2 ~SlamNavController

Item	Content
Function Name	<code>~SlamNavController</code>
Function Declaration	<code>~SlamNavController();</code>
Function Overview	Destructor, releases controller resources
Remarks	Used in conjunction with constructor

### 13.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>bool Initialize();</code>
Function Overview	Initializes SLAM navigation controller, prepares SLAM and navigation functions
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure
Remarks	Must be called before first use

### 13.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>void Shutdown();</code>
Function Overview	Closes controller and releases resources
Remarks	Used in conjunction with <code>Initialize</code> , safely disconnects

### 13.1.5 ActivateSlamMode

Item	Content
Function Name	ActivateSlamMode
Function Declaration	Status ActivateSlamMode(SlamMode mode, std::string map_path = "", int timeout_ms);
Function Overview	Activates SLAM mode and starts mapping or localization mode
Parameter Description	mode: SLAM mode enumeration map_path: Map path (used in localization mode), can be obtained through GetMapPath timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, supports mapping and localization mode switching

### 13.1.6 StartMapping

Item	Content
Function Name	StartMapping
Function Declaration	Status StartMapping(int timeout_ms);
Function Overview	Starts mapping
Parameter Description	timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, mapping mode must be activated first

### 13.1.7 CancelMapping

Item	Content
Function Name	CancelMapping
Function Declaration	Status CancelMapping(int timeout_ms);
Function Overview	Cancels mapping
Parameter Description	timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, cancels current mapping task

### 13.1.8 SaveMap

Item	Content
Function Name	SaveMap
Function Declaration	<code>Status SaveMap(const std::string&amp; map_name, int timeout_ms);</code>
Function Overview	Ends mapping and saves the map
Parameter Description	map_name: Map name timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, must be called in mapping mode

### 13.1.9 LoadMap

Item	Content
Function Name	LoadMap
Function Declaration	<code>Status LoadMap(const std::string&amp; map_name, int timeout_ms);</code>
Function Overview	Loads map and sets it as current map
Parameter Description	map_name: Map name timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, loads map with specified name

### 13.1.10 DeleteMap

Item	Content
Function Name	DeleteMap
Function Declaration	<code>Status DeleteMap(const std::string&amp; map_name, int timeout_ms);</code>
Function Overview	Deletes map
Parameter Description	map_name: Name of map to delete timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, permanently deletes specified map

### 13.1.11 GetMapPath

Item	Content
Function Name	GetMapPath
Function Declaration	<code>Status GetMapPath(const std::string&amp; map_name, std::vector&amp; map_path, int timeout_ms);</code>
Function Overview	Gets map path
Parameter Description	map_name: Map name map_path: Map path (output parameter) timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, gets storage path of specified map

### 13.1.12 GetAllMapInfo

Item	Content
Function Name	GetAllMapInfo
Function Declaration	<code>Status GetAllMapInfo(AllMapInfo&amp; all_map_info, int timeout_ms);</code>
Function Overview	Gets all map information
Parameter Description	all_map_info: All map information (output parameter) timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, gets detailed information of all maps in the system

### 13.1.13 InitPose

Item	Content
Function Name	InitPose
Function Declaration	<code>Status InitPose(const Pose3DEuler&amp; pose, int timeout_ms);</code>
Function Overview	Initializes pose
Parameter Description	<code>pose</code> : Pose information to publish <code>timeout_ms</code> : Timeout time (milliseconds), default value is 15000
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, sets robot initial pose; when publishing pose, a fixed -1.57rad offset needs to be applied to the Yaw direction because there is a -1.57rad offset between the mechanical installation of the LiDAR and the robot body

### 13.1.14 GetCurrentLocalizationInfo

Item	Content
Function Name	GetCurrentLocalizationInfo
Function Declaration	<code>Status GetCurrentLocalizationInfo(LocalizationInfo&amp; pose_info, int timeout_ms);</code>
Function Overview	Gets current pose information
Parameter Description	<code>pose_info</code> : Current position and orientation information (output parameter) <code>timeout_ms</code> : Timeout time (milliseconds)
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, gets robot current pose status



### 13.1.15 ActivateNavMode

Item	Content
Function Name	ActivateNavMode
Function Declaration	<code>Status ActivateNavMode(NavMode mode, std::string map_path = "", int timeout_ms);</code>
Function Overview	Activates navigation mode
Parameter Description	mode: Target navigation mode map_path: Map path (used in grid map mode), can be obtained through GetMapPath timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, activates specified navigation mode

### 13.1.16 SetNavTarget

Item	Content
Function Name	SetNavTarget
Function Declaration	<code>Status SetNavTarget(const NavTarget&amp; goal, int timeout_ms);</code>
Function Overview	Sets global navigation target point and starts navigation task
Parameter Description	goal: Global coordinates of target point timeout_ms: Timeout time (milliseconds)
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, sets navigation target and starts navigation

### 13.1.17 PauseNavTask

Item	Content
Function Name	PauseNavTask
Function Declaration	<code>Status PauseNavTask();</code>
Function Overview	Pauses current navigation task
Return Value	Status::OK indicates success, others indicate failure
Remarks	Non-blocking interface, pauses navigation task

### 13.1.18 ResumeNavTask

Item	Content
Function Name	ResumeNavTask
Function Declaration	<code>Status ResumeNavTask();</code>
Function Overview	Resumes paused navigation task
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Non-blocking interface, resumes paused navigation task

### 13.1.19 CancelNavTask

Item	Content
Function Name	CancelNavTask
Function Declaration	<code>Status CancelNavTask();</code>
Function Overview	Cancels current navigation task
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Non-blocking interface, cancels current navigation task

### 13.1.20 GetNavStatus

Item	Content
Function Name	GetNavStatus
Function Declaration	<code>Status GetNavStatus(NavStatus&amp; nav_status);</code>
Function Overview	Gets navigation status
Parameter Description	<code>nav_status</code> : Navigation status (output parameter)
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Non-blocking interface, gets current navigation status information

### 13.1.21 OpenOdometryStream

Item	Content
Function Name	OpenOdometryStream
Function Declaration	<code>Status OpenOdometryStream();</code>
Function Overview	Open odometry stream
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, check return value to ensure successful execution

### 13.1.22 CloseOdometryStream

Item	Content
Function Name	CloseOdometryStream
Function Declaration	<code>Status CloseOdometryStream();</code>
Function Overview	Close odometry stream
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, used in conjunction with OpenOdometryStream

### 13.1.23 SubscribeOdometry

Item	Content
Function Name	SubscribeOdometry
Function Declaration	<code>void SubscribeOdometry(const OdometryCallback callback);</code>
Function Overview	Subscribe to odometry data
Parameter Description	<code>callback</code> : Processing callback function after receiving odometry data
Remarks	Non-blocking interface, callback function will be called when odometry data is updated

### 13.1.24 UnsubscribeOdometry

Item	Content
Function Name	UnsubscribeOdometry
Function Declaration	<code>void UnsubscribeOdometry();</code>
Function Overview	Unsubscribe from odometry data
Remarks	Non-blocking interface. Used in conjunction with SubscribeOdometry

### 13.1.25 GetPointCloudMap

Item	Content
Function Name	GetPointCloudMap
Function Declaration	<code>Status GetPointCloudMap(PointCloud2&amp; point_cloud_map, int timeout_ms);</code>
Function Overview	Get point cloud map data
Parameter Description	<code>point_cloud_map</code> : Point cloud map data (output parameter) <code>timeout_ms</code> : Timeout duration (milliseconds)
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, gets current point cloud map data

## 13.2 Type Definitions

### 13.2.1 Pose3DEuler —3D Pose Structure

Field Name	Type	Description
position	<code>std::array&lt;double, 3&gt;</code>	Position coordinates (x, y, z)
orientation	<code>std::array&lt;double, 3&gt;</code>	Euler angles (roll, pitch, yaw)

### 13.2.2 NavTarget —Navigation Target Point Structure

Field Name	Type	Description
id	<code>int</code>	Target point ID
frame_id	<code>std::string</code>	Target point coordinate frame ID
goal	<code>Pose3DEuler</code>	Target point pose

### 13.2.3 LocalizationInfo —Pose Information Structure

Field Name	Type	Description
is_localization	<code>bool</code>	Whether localized
pose	<code>Pose3DEuler</code>	Current pose

### 13.2.4 NavStatus —Navigation Status Structure

Field Name	Type	Description
id	<code>int</code>	Target point ID, -1 indicates no target point
status	<code>NavStatusType</code>	Navigation status type
message	<code>std::string</code>	Navigation status message

### 13.2.5 PolyRegion —Polygon Region Structure

Field Name	Type	Description
points	<code>std::vector&lt;Point2D&gt;</code>	Polygon vertex list

### 13.2.6 Point2D —2D Point Structure

Field Name	Type	Description
x	double	X coordinate
y	double	Y coordinate

## 13.3 Enumeration Type Definitions

### 13.3.1 SlamMode —SLAM Mode Enumeration

Enum Value	Value	Description
IDLE	0	Idle mode
LOCALIZATION	1	Localization mode
MAPPING	2	Mapping mode

### 13.3.2 NavMode —Navigation Mode Enumeration

Enum Value	Value	Description
IDLE	0	Idle mode
GRID_MAP	1	Grid map navigation mode

### 13.3.3 NavStatusType —Navigation Status Type Enumeration

Enum Value	Value	Description
NONE	0	No status
RUNNING	1	Running
END_SUCCESS	2	Successfully ended
END_FAILED	3	Failed to end
PAUSE	4	Paused
CONTINUE	5	Continue
CANCEL	6	Canceled

## 13.4 SLAM Navigation Control Introduction

The robot's SLAM navigation control service can be divided into SLAM functions and navigation functions.

- In SLAM functions, corresponding interfaces can be called to implement mapping, localization, map management and other functions.
- In navigation functions, corresponding interfaces can be called to implement target navigation, navigation control and other functions.

### 13.4.1 Applicable Scenarios and Scope

- Static indoor flat areas smaller than 100 m × 100 m with rich features. Do not exceed the recommended range.
- This functionality is applicable to the education and research industry and is not recommended for commercial applications. For commercial use, please contact sales.

### 13.4.2 SLAM Function Flow

Function	Operation Flow
Mapping	Activate mapping mode → Start mapping → Save map
Map Management	Load map, get map information, delete map, get map path, etc.

### 13.4.3 Navigation Function Flow

Function	Operation Flow
Localization	Load map → Activate localization mode → Initialize pose → Get localization status
Navigation	Localization success → Activate navigation mode → Set target pose → Get navigation status
Navigation Control	Set target pose → PauseNavTask navigation → ResumeNavTask navigation → CancelNavTask navigation

### 13.4.4 Localization Mode Initialization

When SLAM is in localization mode, an initial pose can be specified to quickly complete relocalization and initialization. For large-scale maps, specifying the initial pose is mandatory.

#### Small Map Mode

满足如下条件:

The following conditions must be met:

- Condition 1: The map should not be too large. For example, in a single room, it is best to keep the map area within 10m × 10m.

- Condition 2: Modify the configuration to adapt to this mode:

```
# Log in to the robot
ssh eame@192.168.54.119
# Modify the following configuration
# vim /opt/eame/eamegrapher_3d/share/eamegrapher_3d/config/params.yaml
reloc_options: true

# After modifying the YAML file for the first time, restart the SLAM module for the
↪change to take effect:
sudo systemctl restart slam.service
```

## Large Map Mode

The following conditions must be met:

- Condition 1: The robot must be located at the mapping origin (the starting position when mapping began), and the robot's orientation must remain consistent.
- Condition 2: Modify the configuration to adapt to this mode:

When using the SDK for SLAM navigation (unlike the app, which allows convenient visual positioning), you must modify the SLAM configuration to fix the map orientation and facilitate localization:

```
# Log in to the robot
ssh eame@192.168.54.119
# Modify the following configuration
# vim /opt/eame/eamegrapher_3d/share/eamegrapher_3d/config/params.yaml
align_map: false

# After modifying the YAML file for the first time, restart the SLAM module for the
↪change to take effect:
sudo systemctl restart slam.service
```

- Condition 3: When initializing the pose, apply a 180° (3.14 rad) offset to the yaw angle:

because the LiDAR's mechanical installation differs from the robot body orientation by 180°.

### 13.4.5 Map Noise Removal and Obstacle Addition

- Software Name: GIMP
- Download Link: <https://www.gimp.org/downloads/>
- Operating System: Ubuntu

- File to Edit: `/home/eame/cust_para/maps/${map_name}/map/map.pgm` Log in to the robot (ssh [eame@192.168.54.119](mailto:eame@192.168.54.119)), open the .pgm map file with GIMP for editing, and replace the original file after modifications are complete.
- Editing Tutorial Video:



---

## Robot Main Control Service (Python)

---

---

Provides robot system main controller. Through the `MagicRobot` class, you can perform resource initialization, manage communication connections, and access various sub-controllers such as motion controllers, audio, state monitoring, and sensor controllers.

### 14.1 Interface Definition

`MagicRobot` is the unified entry class for the robot SDK.

#### 14.1.1 `MagicRobot`

Item	Content
Class Name	<code>MagicRobot</code>
Constructor	<code>robot = MagicRobot()</code>
Function Overview	Constructor, creates <code>MagicRobot</code> instance.
Notes	Constructs internal state.

## 14.1.2 initialize

Item	Content
Function Name	<code>initialize</code>
Function Declaration	<code>bool initialize(str local_ip)</code>
Function Overview	Initialize robot system, including controllers and network modules.
Parameter Description	<code>local_ip</code> : Local communication IP address.
Return Value	<code>True</code> indicates success, <code>False</code> indicates failure.
Notes	Must be called before first use.

## 14.1.3 shutdown

Item	Content
Function Name	<code>shutdown</code>
Function Declaration	<code>void shutdown()</code>
Function Overview	Shutdown robot system and release resources.
Notes	Used in conjunction with <code>initialize</code> .

## 14.1.4 connect

Item	Content
Function Name	<code>connect</code>
Function Declaration	<code>Status connect()</code>
Function Overview	Establish communication connection with robot service.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, must be called after initialization.

## 14.1.5 disconnect

Item	Content
Function Name	<code>disconnect</code>
Function Declaration	<code>Status disconnect()</code>
Function Overview	Disconnect from robot service.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, used in conjunction with <code>connect</code> .

### 14.1.6 get\_sdk\_version

Item	Content
Function Name	<code>get_sdk_version</code>
Function Declaration	<code>str get_sdk_version()</code>
Function Overview	Get current SDK version number.
Return Value	SDK version string (e.g., 0.0.1).
Notes	Non-blocking interface, convenient for debugging or log marking.

### 14.1.7 get\_motion\_control\_level

Item	Content
Function Name	<code>get_motion_control_level</code>
Function Declaration	<code>ControllerLevel get_motion_control_level()</code>
Function Overview	Get current motion control level (high-level/low-level).
Return Value	<code>ControllerLevel</code> enumeration value.
Notes	Non-blocking interface, used to determine current control permissions.

### 14.1.8 set\_motion\_control\_level

Item	Content
Function Name	<code>set_motion_control_level</code>
Function Declaration	<code>Status set_motion_control_level(ControllerLevel level)</code>
Function Overview	Set current motion control level.
Parameter Description	<code>level</code> : Control permission enumeration value.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates successful setting.
Notes	Blocking interface, used when switching control modes.

### 14.1.9 get\_high\_level\_motion\_controller

Item	Content
Function Name	<code>get_high_level_motion_controller</code>
Function Declaration	<code>HighLevelMotionController get_high_level_motion_controller()</code>
Function Overview	Get high-level motion controller object.
Return Value	<code>HighLevelMotionController</code> object, used to call high-level control interfaces.
Notes	Non-blocking interface, encapsulates gait, tricks, remote control, etc.

### 14.1.10 get\_low\_level\_motion\_controller

Item	Content
Function Name	<code>get_low_level_motion_controller</code>
Function Declaration	<code>LowLevelMotionController get_low_level_motion_controller()</code>
Function Overview	Get low-level motion controller object.
Return Value	<code>LowLevelMotionController</code> object, used to control joints or motors.
Notes	Non-blocking interface, directly controls joint motors, gets IMU data, etc.

### 14.1.11 get\_audio\_controller

Item	Content
Function Name	<code>get_audio_controller</code>
Function Declaration	<code>AudioController get_audio_controller()</code>
Function Overview	Get audio controller object.
Return Value	<code>AudioController</code> object, used for audio control.
Notes	Non-blocking interface, plays audio and controls volume.

### 14.1.12 get\_sensor\_controller

Item	Content
Function Name	<code>get_sensor_controller</code>
Function Declaration	<code>SensorController get_sensor_controller()</code>
Function Overview	Get sensor controller object.
Return Value	<code>SensorController</code> object, used to access sensor data.
Notes	Non-blocking interface, encapsulates LiDAR, RGBD, etc. reading.

### 14.1.13 get\_state\_monitor

Item	Content
Function Name	<code>get_state_monitor</code>
Function Declaration	<code>StateMonitor get_state_monitor()</code>
Function Overview	Get state monitor object.
Return Value	<code>StateMonitor</code> object, used to get current robot state information.
Notes	Non-blocking interface, encapsulates reading of BMS, faults, and other state information.

#### 14.1.14 get\_slam\_nav\_controller

项目	内容
函数名	get_slam_nav_controller
函数声明	SlamNavController get_slam_nav_controller();
功能概述	获取 SLAM 与导航控制器对象。
返回值	引用类型，用于建图与定位。
备注	非阻塞接口，用于机器人 SLAM 建图与自主导航功能。



---

## High-Level Motion Control Service (Python)

---

---

Provides robot system high-level motion control service. Through the `HighLevelMotionController`, you can control robot gait, tricks, and remote control via RPC communication.

### 15.1 Interface Definition

`HighLevelMotionController` is a high-level motion controller for semantic control, supporting control operations such as walking, tricks, head movement, etc., encapsulating low-level details for upper system calls.

#### 15.1.1 `HighLevelMotionController`

Item	Content
Class Name	<code>HighLevelMotionController</code>
Constructor	<code>controller = HighLevelMotionController()</code>
Function Overview	Constructor, initializes high-level controller state
Notes	Constructs internal control resources

## 15.1.2 initialize

Item	Content
Function Name	<code>initialize</code>
Function Declaration	<code>bool initialize()</code>
Function Overview	Initialize controller, prepare high-level control functions
Return Value	<code>True</code> indicates success, <code>False</code> indicates failure
Notes	Must be called before first use

## 15.1.3 shutdown

Item	Content
Function Name	<code>shutdown</code>
Function Declaration	<code>void shutdown()</code>
Function Overview	Shutdown controller and release resources
Notes	Used in conjunction with <code>initialize</code> , safely disconnect

## 15.1.4 set\_gait

Item	Content
Function Name	<code>set_gait</code>
Function Declaration	<code>Status set_gait(GaitMode gait_mode, int timeout_ms)</code>
Function Overview	Set robot gait mode (such as recovery stand, balance stand, humanoid walk, etc.)
Parameter Description	<code>gait_mode</code> : Gait control enumeration
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success
Notes	Blocking interface, can switch between multiple gait modes

## 15.1.5 get\_gait

Item	Content
Function Name	<code>get_gait</code>
Function Declaration	<code>Status get_gait()</code>
Function Overview	Get robot gait mode (such as recovery stand, balance stand, humanoid walk, etc.)
Return Value	<code>Status</code> object, contains current gait mode information
Notes	Blocking interface, gets current gait mode



### 15.1.6 execute\_trick

Item	Content
Function Name	execute_trick
Function Declaration	Status execute_trick(TrickAction trick_action, int timeout_ms)
Function Overview	Execute trick actions (such as welcom, etc.)
Parameter Description	trick_action: Trick action identifier
Return Value	Status object, Status.code == ErrorCode.OK indicates success
Notes	Blocking interface, ensure robot can currently execute tricksNote: Trick actions must be performed in GaitMode.GAIT_BALANCE_STAND(46) gait

### 15.1.7 send\_joystick\_command

Item	Content
Function Name	send_joystick_command
Function Declaration	Status send_joystick_command(JoystickCommand joy_command)
Function Overview	Send real-time joystick control commands
Parameter Description	joy_command: Control data containing joystick coordinates
Return Value	Status object, Status.code == ErrorCode.OK indicates success
Notes	Non-blocking interface, recommended sending frequency is 20Hz

### 15.1.8 head\_move

Item	Content
Function Name	head_move
Function Declaration	Status head_move(float shake_angle, int timeout_ms);
Function Overview	Control robot head swinging motion
Parameter Description	shake_angle: Head swing angle, unit: rad, range: [-0.698, 0.698]timeout_ms: Timeout duration, default 5000 milliseconds
Return Value	Status::OK indicates success, others indicate failure
Notes	Blocking interface, controls robot head left-right swinging motion

## 15.2 Type Definitions

### 15.2.1 JoystickCommand —High-Level Motion Control Joystick Command Structure

Field Name	Type	Description
left_x_axis	float	Left joystick X-axis direction value (-1.0: left, 1.0: right)
left_y_axis	float	Left joystick Y-axis direction value (-1.0: down, 1.0: up)
right_x_axis	float	Right joystick X-axis direction value (rotation -1.0: left, 1.0: right)
right_y_axis	float	Right joystick Y-axis direction value (purpose not yet defined)

## 15.3 Enumeration Type Definitions


### 15.3.1 GaitMode —Robot Gait Mode Enumeration

Enumeration Value	Value	Description
GAIT_PASSIVE	0	Passive
GAIT_RECOVERY_STAND	1	Recovery Stand
GAIT_BALANCE_STAND	46	Balance Stand (supports movement)
GAIT_HUMANOID_WALK	79	Humanoid Walk
GAIT_LOWLEVEL_SDK	200	Low-Level Control SDK Mode

## 15.3.2 TrickAction —Trick Action Command Enumeration


Enumeration Value	Value	Description
ACTION_SHAKE_LEFT_HAND_REACHOUT	215	Handshake (Left Hand) - Reach Out
ACTION_SHAKE_LEFT_HAND_WITHDRAW	216	Handshake (Left Hand) - Withdraw
ACTION_SHAKE_RIGHT_HAND_REACHOUT	217	Handshake (Right Hand) - Reach Out
ACTION_SHAKE_RIGHT_HAND_WITHDRAW	218	Handshake (Right Hand) - Withdraw
ACTION_SHAKE_HEAD	220	Shake Head
ACTION_LEFT_GREETING	300	Greeting (Left Hand)
ACTION_RIGHT_GREETING	301	Greeting (Right Hand)
ACTION_TRUN_LEFT_INTRODUCE_HIGH	304	Turn Left Introduce - High
ACTION_TRUN_LEFT_INTRODUCE_LOW	305	Turn Left Introduce - Low
ACTION_TRUN_RIGHT_INTRODUCE_HIGH	306	Turn Right Introduce - High
ACTION_TRUN_RIGHT_INTRODUCE_LOW	307	Turn Right Introduce - Low
ACTION_WELCOME	340	Welcome
FLY_KISS_LEFT	408	Air Kiss - Left Hand
FLY_KISS_RIGHT	409	Air Kiss - Right Hand
SUPERMAN_WAVE	410	Superman Wave
CLAP_HAND	411	Clap Hands
HOLD_CERT_REACHOUT	412	Hold Certificate - Reach Out
HOLD_CERT_WITHDRAW	413	Hold Certificate - Withdraw
HUG_REACHOUT	414	Hug with Both Hands - Reach Out
HUG_WITHDRAW	415	Hug with Both Hands - Withdraw
TRUN_WAVE_LEFT	417	Turn and Wave - Left Hand
TRUN_WAVE_RIGHT	418	Turn and Wave - Right Hand
RIGHT_HAND_SALUTE	419	Right Hand Salute

## 15.4 Joystick Diagram



1. The X-axis and Y-axis value ranges for left and right joysticks are  $[-1.0, 1.0]$ ;
2. The up/right direction of the left and right joystick X-axis and Y-axis is positive, as shown in the diagram;

## 15.5 Head Movement Range Diagram



- Movement Range  $[-40^\circ, 40^\circ]$  ( $[-0.698\text{rad}, 0.698\text{rad}]$ )

## 15.6 High-Level Motion Control Robot State Introduction


Robot motion includes recovery stand, balance stand, basic motion, and trick action states. During operation, the robot switches between different states through a state machine to achieve different control tasks. The explanations for each state are as follows:

- **Recovery Stand:** Recovery stand is the state connecting robot suspension landing and balance stand. The robot needs to enter the balance stand state before calling corresponding motion services to achieve robot control.
- **Balance Stand:** In the balance stand state, you can call various SDK interfaces to achieve robot trick actions and

basic motion control.

- **Basic Motion:** During motion execution, you can call SDK interfaces to make the robot enter different gaits.
- **Trick Actions:** When entering the special action execution state, other motion control services will be suspended first, waiting for the current action to complete and enter the balance stand state before taking effect again.


Robot state switching mechanism;



## 15.7 High-Level Motion Control Interface

Robot high-level motion control services can be divided into basic motion control and trick action control.

- In basic motion control services, you can call corresponding interfaces to switch robot walking gaits according to different terrain scenarios and task requirements.
- In trick action control services, you can call corresponding interfaces to achieve robot built-in special tricks, such as Celebrate, handshake, greeting, etc.



### 15.7.1 Gait Switching

Current Gait	Gait Switching Process	Diagram
Recovery Stand		
Balance Stand		
Arm Swing Walk		
Humanoid Walk		

## 15.7.2 Trick Execution

Trick	Trick Execution Process	Diagram
Welcome		
Shake Head		
Greeting (Left Hand)		
Greeting (Right Hand)		
Handshake (Left Hand)		
Handshake (Right Hand)		
Turn Left Introduction		
Turn Right Introduction		



---

## Low-Level Motion Control Service (Python)

---

---

Provides robot system low-level motion control service. Through the `LowLevelMotionController`, you can control robot joints and obtain status via topic communication.

### 16.1 Interface Definition

`LowLevelMotionController` is a motion controller for low-level development, supporting direct control and state subscription of motion components such as arms, legs, head, waist, hands, etc., as well as body IMU data acquisition.

#### 16.1.1 `LowLevelMotionController`

Item	Content
Class Name	<code>LowLevelMotionController</code>
Constructor	<code>controller = LowLevelMotionController()</code>
Function Overview	Constructor, initializes low-level controller object.
Notes	Constructs internal resources.

## 16.1.2 initialize

Item	Content
Function Name	<code>initialize</code>
Function Declaration	<code>bool initialize()</code>
Function Overview	Initialize controller, establish low-level connection.
Return Value	<code>True</code> indicates success, <code>False</code> indicates failure.
Notes	Must be initialized on first call.

## 16.1.3 shutdown

Item	Content
Function Name	<code>shutdown</code>
Function Declaration	<code>void shutdown()</code>
Function Overview	Shutdown controller, release low-level resources.
Notes	Used in conjunction with <code>initialize</code> .

## 16.1.4 subscribe\_arm\_state

Item	Content
Function Name	<code>subscribe_arm_state</code>
Function Declaration	<code>void subscribe_arm_state(callback)</code>
Function Overview	Subscribe to arm joint state data
Parameter Description	<code>callback</code> : Data processing function, signature is <code>callback(data: JointState) -&gt; None</code>
Notes	Non-blocking interface.

## 16.1.5 publish\_arm\_command

Item	Content
Function Name	<code>publish_arm_command</code>
Function Declaration	<code>Status publish_arm_command(JointCommand command)</code>
Function Overview	Publish arm control commands
Parameter Description	<code>command</code> : Target position/velocity, etc.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Non-blocking interface.

### 16.1.6 subscribe\_leg\_state

Item	Content
Function Name	subscribe_leg_state
Function Declaration	<code>void subscribe_leg_state(callback)</code>
Function Overview	Subscribe to leg joint state data
Parameter Description	callback: Data processing function, signature is <code>callback(data: JointState) -&gt; None</code>
Notes	Non-blocking interface.

### 16.1.7 publish\_leg\_command

Item	Content
Function Name	publish_leg_command
Function Declaration	<code>Status publish_leg_command(JointCommand command)</code>
Function Overview	Publish leg control commands
Parameter Description	command: Target position/velocity, etc.
Return Value	Status object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Non-blocking interface, called when publishing or subscribing.

### 16.1.8 subscribe\_head\_state

Item	Content
Function Name	subscribe_head_state
Function Declaration	<code>void subscribe_head_state(callback)</code>
Function Overview	Subscribe to head joint state data
Parameter Description	callback: Data processing function, signature is <code>callback(data: JointState) -&gt; None</code>
Notes	Non-blocking interface.

### 16.1.9 publish\_head\_command

Item	Content
Function Name	publish_head_command
Function Declaration	<code>Status publish_head_command(JointCommand command)</code>
Function Overview	Publish head control commands
Parameter Description	command: Target position/velocity, etc.
Return Value	Status object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Non-blocking interface.

### 16.1.10 subscribe\_waist\_state

Item	Content
Function Name	<code>subscribe_waist_state</code>
Function Declaration	<code>void subscribe_waist_state(callback)</code>
Function Overview	Subscribe to waist joint state data
Parameter Description	callback: Data processing function, signature is <code>callback(data: JointState) -&gt; None</code>
Notes	Non-blocking interface.

### 16.1.11 publish\_waist\_command

Item	Content
Function Name	<code>publish_waist_command</code>
Function Declaration	<code>Status publish_waist_command(JointCommand command)</code>
Function Overview	Publish waist control commands
Parameter Description	command: Target position/velocity, etc.
Return Value	Status object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Non-blocking interface.

### 16.1.12 subscribe\_hand\_state

Item	Content
Function Name	<code>subscribe_hand_state</code>
Function Declaration	<code>void subscribe_hand_state(callback)</code>
Function Overview	Subscribe to hand state data
Parameter Description	callback: Data processing function, signature is <code>callback(data: HandState) -&gt; None</code>
Notes	Non-blocking interface.

### 16.1.13 publish\_hand\_command

Item	Content
Function Name	<code>publish_hand_command</code>
Function Declaration	<code>Status publish_hand_command(HandCommand command)</code>
Function Overview	Publish hand control commands
Parameter Description	command: Hand joint target positions, etc.
Return Value	Status object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Non-blocking interface.

### 16.1.14 subscribe\_body\_imu

Item	Content
Function Name	subscribe_body_imu
Function Declaration	<code>void subscribe_body_imu(callback)</code>
Function Overview	Subscribe to body IMU data
Parameter Description	callback: IMU data processing function, signature is <code>callback(data: Imu) -&gt; None</code>
Notes	Non-blocking interface.

### 16.1.15 subscribe\_estimator\_state

Item	Content
Function Name	subscribe_estimator_state
Function Declaration	<code>void subscribe_estimator_state(callback)</code>
Function Overview	Subscribe to body Estimator state data
Parameter Description	callback: Estimator state data processing function, signature is <code>callback(data: Imu) -&gt; None</code>
Notes	Non-blocking interface.

### 16.1.16 unsubscribe\_arm\_state

Item	Content
Function Name	unsubscribe_arm_state
Function Declaration	<code>void unsubscribe_arm_state()</code>
Function Overview	Unsubscribe from arm joint state data
Notes	Non-blocking interface, used in conjunction with <code>subscribe_arm_state</code> .

### 16.1.17 unsubscribe\_leg\_state

Item	Content
Function Name	unsubscribe_leg_state
Function Declaration	<code>void unsubscribe_leg_state()</code>
Function Overview	Unsubscribe from leg joint state data
Notes	Non-blocking interface, used in conjunction with <code>subscribe_leg_state</code> .

### 16.1.18 unsubscribe\_head\_state

Item	Content
Function Name	<code>unsubscribe_head_state</code>
Function Declaration	<code>void unsubscribe_head_state()</code>
Function Overview	Unsubscribe from head joint state data
Notes	Non-blocking interface, used in conjunction with <code>subscribe_head_state</code> .

### 16.1.19 unsubscribe\_waist\_state

Item	Content
Function Name	<code>unsubscribe_waist_state</code>
Function Declaration	<code>void unsubscribe_waist_state()</code>
Function Overview	Unsubscribe from waist joint state data
Notes	Non-blocking interface, used in conjunction with <code>subscribe_waist_state</code> .

### 16.1.20 unsubscribe\_hand\_state

Item	Content
Function Name	<code>unsubscribe_hand_state</code>
Function Declaration	<code>void unsubscribe_hand_state()</code>
Function Overview	Unsubscribe from hand state data
Notes	Non-blocking interface, used in conjunction with <code>subscribe_hand_state</code> .

### 16.1.21 unsubscribe\_body\_imu

Item	Content
Function Name	<code>unsubscribe_body_imu</code>
Function Declaration	<code>void unsubscribe_body_imu()</code>
Function Overview	Unsubscribe from body IMU data
Notes	Non-blocking interface, used in conjunction with <code>subscribe_body_imu</code> .

### 16.1.22 unsubscribe\_estimator\_state

Item	Content
Function Name	unsubscribe_estimator_state
Function Declaration	void unsubscribe_estimator_state()
Function Overview	Unsubscribe from body estimator state data
Notes	Non-blocking interface, used in conjunction with subscribe_estimator_state.

## 16.2 Type Definitions

### 16.2.1 SingleHandJointCommand —Single Hand Joint Control Command

Field Name	Type	Description
operation_mode	int16_t	Control mode (such as position, torque, impedance, etc.), default value is 0
pos	list[float]	Desired position array (7 degrees of freedom)

### 16.2.2 HandCommand —Complete Hand Control Command

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
cmd	list[SingleHandJointCommand]	Control command array, left hand and right hand in order

### 16.2.3 SingleHandJointState —Single Hand Joint State

Field Name	Type	Description
status_word	int16_t	Status
pos	list[float]	Actual position (unit depends on controller definition)
toq	list[float]	Actual torque (unit: Nm)
cur	list[float]	Actual current (unit: A)
error_code	int16_t	Error code (0 indicates normal)

## 16.2.4 HandState —Complete Hand Status Information

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
state	list[SingleHandJointState]	All hand joint states (total two), left hand and right hand in order

## 16.2.5 SingleJointCommand —Single Joint Control Command

Field Name	Type	Description
operation_mode	int16_t	Control mode identifier: • 200 = Standby mode • 3 = Parallel triple-loop control (MIT mode) • 4 = Serial triple-loop control
pos	float	Target position (unit: rad or m, depends on joint type)
vel	float	Target velocity (unit: rad/s or m/s)
toq	float	Target torque (unit: Nm)
kp	float	Position loop control gain (proportional term)
kd	float	Velocity loop control gain (derivative term)

- For joints 1-5 of the arm, the `operation_mode` needs to be switched from mode 200 (standby) to mode 3 (parallel triple-loop control, MIT mode) before sending commands.
- For joint 1 of the waist, the `operation_mode` needs to be switched from mode 200 (standby) to mode 3 (parallel triple-loop control, MIT mode) before sending commands.
- For joints 1-6 of the legs, the `operation_mode` needs to be switched from mode 200 (standby) to mode 3 (parallel triple-loop control, MIT mode) before sending commands.
- The head joint uses pure position control and does not require setting `operation_mode`.

## 16.2.6 JointCommand —Joint Control Command

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
joints	list[SingleJointCommand]	Joint control command array



## 16.2.7 SingleJointState —Single Joint Status

Field Name	Type	Description
status_word	int16_t	Current joint status (custom state machine encoding)
posH	float	Actual position (high encoder reading, may be redundant encoder)
posL	float	Actual position (low encoder reading)
vel	float	Current velocity (unit: rad/s or m/s)
toq	float	Current torque (unit: Nm)
current	float	Current current (unit: A)
err_code	int16_t	Error code (such as encoder exception, motor overcurrent, etc.)

## 16.2.8 JointState —Joint State

Field Name	Type	Description
timestamp	int64_t	Timestamp (unit: nanoseconds)
joints	list[SingleJointState]	Joint state array

## 16.2.9 EstimatorState —State Estimation Data

Field Name	Type	Description
w_base_pos	list[float]	Robot base position(m) in the world frame
w_com_pos	list[float]	Center of mass position(m) in the world frame
w_com_vel	list[float]	Center of mass linear velocity(m/s) in world frame
w_base_vel	list[float]	Robot base linear velocity(m/s) in world frame
b_base_vel	list[float]	Robot base linear velocity(m/s) in body frame

### 16.2.10 Joint Motor Order

#### Head Joint

Index	Joint Name
0	head_joint

## Arm Joints

Index	Joint Name
0	left_shoulder_pitch_joint
1	left_shoulder_roll_joint
2	left_shoulder_yaw_joint
3	left_elbow_joint
4	left_wrist_yaw_joint
5	left_wrist_roll_joint
6	left_wrist_pitch_joint
7	right_shoulder_pitch_joint
8	right_shoulder_roll_joint
9	right_shoulder_yaw_joint
10	right_elbow_roll_joint
11	right_wrist_yaw_joint
12	right_wrist_roll_joint
13	right_wrist_pitch_joint

## Waist Joint

Index	Joint Name
0	waist_yaw_joint

## Leg Joints


Index	Joint Name
0	left_hip_pitch_joint
1	left_hip_roll_joint
2	left_hip_yaw_joint
3	left_knee_joint
4	left_ankle_pitch_joint
5	left_ankle_roll_joint
6	right_hip_pitch_joint
7	right_hip_roll_joint
8	right_hip_yaw_joint
9	right_knee_joint
10	right_ankle_pitch_joint
11	right_ankle_roll_joint

## 16.3 URDF Reference

Robot URDF

## 16.4 Low-Level Motion Control Robot State Introduction

Robot low-level motion mainly develops three-loop control of joints for developers to perform secondary development of robot motion capabilities. Basic control state switching mechanism:



## 16.5 Notice:

- When using subscription-type SDK interfaces such as Subscribe, do not perform blocking operations within the callback function. Doing so may cause message congestion, processing delays, or even unexpected errors.
- The Z1 robot's upper arm joints have 5-degree-of-freedom and 7-degree-of-freedom SKU versions. For different versions, the joint motor sequence and names are used in order, and nonexistent joints can be ignored.



---

## Sensor Control Service (Python)

---

---

Provides robot system sensor (LiDAR/RGBD camera/binocular camera) services. Through the `SensorController`, you can control robot sensors and obtain status via RPC and topic methods.

### 17.1 Interface Definition

`SensorController` is a management class that encapsulates various robot sensors, supporting initialization, control, and data subscription of LiDAR, RGBD cameras, and binocular cameras.

#### 17.1.1 `SensorController`

Item	Content
Class Name	<code>SensorController</code>
Constructor	<code>controller = SensorController()</code>
Function Overview	Constructor, initializes sensor controller object.
Notes	Constructs internal state.

## 17.1.2 initialize

Item	Content
Function Name	<code>initialize</code>
Function Declaration	<code>bool initialize()</code>
Function Overview	Initialize controller, including resource allocation and driver loading.
Return Value	<code>True</code> indicates success, <code>False</code> indicates failure.
Notes	Object must be constructed before calling.

## 17.1.3 shutdown

Item	Content
Function Name	<code>shutdown</code>
Function Declaration	<code>void shutdown()</code>
Function Overview	Close all sensor connections and release resources.
Notes	Used in conjunction with <code>initialize</code> .

## 17.1.4 open\_lidar

Item	Content
Function Name	<code>open_lidar</code>
Function Declaration	<code>Status open_lidar()</code>
Function Overview	Open LiDAR.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface.

## 17.1.5 close\_lidar

Item	Content
Function Name	<code>close_lidar</code>
Function Declaration	<code>Status close_lidar()</code>
Function Overview	Close LiDAR.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, used in conjunction with <code>open</code> function.

### 17.1.6 open\_head\_rgbd\_camera

Item	Content
Function Name	open_head_rgbd_camera
Function Declaration	Status open_head_rgbd_camera()
Function Overview	Open head RGBD camera.
Return Value	Status object, Status.code == ErrorCode.OK indicates success.
Notes	Blocking interface.

### 17.1.7 close\_head\_rgbd\_camera

Item	Content
Function Name	close_head_rgbd_camera
Function Declaration	Status close_head_rgbd_camera()
Function Overview	Close head RGBD camera.
Return Value	Status object, Status.code == ErrorCode.OK indicates success.
Notes	Blocking interface, used in conjunction with open function.

### 17.1.8 open\_binocular\_camera

Item	Content
Function Name	open_binocular_camera
Function Declaration	Status open_binocular_camera()
Function Overview	Open binocular camera.
Return Value	Status object, Status.code == ErrorCode.OK indicates success.
Notes	Blocking interface.

### 17.1.9 close\_binocular\_camera

Item	Content
Function Name	close_binocular_camera
Function Declaration	Status close_binocular_camera()
Function Overview	Close binocular camera.
Return Value	Status object, Status.code == ErrorCode.OK indicates success.
Notes	Blocking interface, used in conjunction with open function.

### 17.1.10 subscribe\_lidar\_imu

Item	Content
Function Name	subscribe_lidar_imu
Function Declaration	<code>void subscribe_lidar_imu(callback)</code>
Function Overview	Subscribe to LiDAR IMU data
Parameter Description	callback: Data processing function after receiving data, signature is <code>callback(data: Imu) -&gt; None</code>
Notes	Non-blocking interface, callback function will be called when data is updated.

### 17.1.11 subscribe\_lidar\_point\_cloud

Item	Content
Function Name	subscribe_lidar_point_cloud
Function Declaration	<code>void subscribe_lidar_point_cloud(callback)</code>
Function Overview	Subscribe to LiDAR point cloud data
Parameter Description	callback: Point cloud processing function after receiving data, signature is <code>callback(data: PointCloud2) -&gt; None</code>
Notes	Non-blocking interface, callback function will be called when data is updated.

### 17.1.12 subscribe\_head\_rgb\_color\_image

Item	Content
Function Name	subscribe_head_rgb_color_image
Function Declaration	<code>void subscribe_head_rgb_color_image(callback)</code>
Function Overview	Subscribe to head RGB color image data
Parameter Description	callback: Image processing function after receiving data, signature is <code>callback(data: Image) -&gt; None</code>
Notes	Non-blocking interface, callback function will be called when data is updated.



### 17.1.13 subscribe\_head\_rgbd\_depth\_image

Item	Content
Function Name	subscribe_head_rgbd_depth_image
Function Declaration	<code>void subscribe_head_rgbd_depth_image(callback)</code>
Function Overview	Subscribe to head RGBD depth image data
Parameter Description	callback: Depth image processing function after receiving data, signature is callback(data: Image) -> None
Notes	Non-blocking interface, callback function will be called when data is updated.

### 17.1.14 subscribe\_head\_rgbd\_camera\_info

Item	Content
Function Name	subscribe_head_rgbd_camera_info
Function Declaration	<code>void subscribe_head_rgbd_camera_info(callback)</code>
Function Overview	Subscribe to head RGBD camera parameter data
Parameter Description	callback: Camera intrinsic parameter processing function after receiving data, signature is callback(data: CameraInfo) -> None
Notes	Non-blocking interface, callback function will be called when data is updated.

### 17.1.15 subscribe\_binocular\_image

Item	Content
Function Name	subscribe_binocular_image
Function Declaration	<code>void subscribe_binocular_image(callback)</code>
Function Overview	Subscribe to binocular camera image frame data
Parameter Description	callback: Binocular camera data processing function after receiving data, signature is callback(data: BinocularCameraFrame) -> None
Notes	Non-blocking interface, callback function will be called when data is updated.

### 17.1.16 subscribe\_binocular\_camera\_info

Item	Content
Function Name	subscribe_binocular_camera_info
Function Declaration	void subscribe_binocular_camera_info(callback)
Function Overview	Subscribe to binocular camera parameter data
Parameter Description	callback: Camera intrinsic parameter processing function after receiving data, signature is callback(data: CameraInfo) -> None
Notes	Non-blocking interface, callback function will be called when data is updated.

## 17.2 Data Types

### 17.2.1 Imu

IMU data structure, containing sensor data such as attitude, angular velocity, linear acceleration, etc.

Field Name	Type	Description
timestamp	int64_t	Timestamp (nanoseconds)
temperature	float	Temperature (Celsius)
orientation	Quaternion	Attitude quaternion
angular_velocity	Vector3	Angular velocity (rad/s)
linear_acceleration	Vector3	Linear acceleration (m/s <sup>2</sup> )

### 17.2.2 PointCloud2

Point cloud data structure, containing 3D point cloud information.

Field Name	Type	Description
header	Header	Standard message header (timestamp + frame_id)
height	int32_t	Point cloud height (number of rows)
width	int32_t	Point cloud width (number of columns)
fields	list[PointField]	Point field array
is_bigendian	bool	Byte order
point_step	int32_t	Number of bytes per point
row_step	int32_t	Number of bytes per row
data	list[uint8_t]	Raw point cloud data (packed by field)
is_dense	bool	Whether it is a dense point cloud (no invalid points)

### 17.2.3 Image

Image data structure, supporting multiple encoding formats.

Field Name	Type	Description
header	Header	Standard message header (timestamp + frame_id)
height	int32_t	Image height (pixels)
width	int32_t	Image width (pixels)
encoding	str	Image encoding type, such as “rgb8” , “mono8” , “bgr8”
is_bigendian	bool	Whether data is in big-endian mode
step	int32_t	Number of bytes per image row
data	list[uint8_t]	Raw image byte data

### 17.2.4 CameraInfo

Camera intrinsic parameters and distortion information, usually published together with Image messages.

Field Name	Type	Description
header	Header	Standard message header (timestamp + frame_id)
height	int32_t	Image height (number of rows)
width	int32_t	Image width (number of columns)
distortion_model	str	Distortion model, e.g., “plumb_bob”
D	list[double]	Distortion parameter array
K	list[double]	Camera intrinsic matrix (9 elements)
R	list[double]	Rectification matrix (9 elements)
P	list[double]	Projection matrix (12 elements)
binning_x	int32_t	Horizontal binning coefficient
binning_y	int32_t	Vertical binning coefficient
roi_x_offset	int32_t	ROI start x
roi_y_offset	int32_t	ROI start y
roi_height	int32_t	ROI height
roi_width	int32_t	ROI width
roi_do_rectify	bool	Whether to perform rectification

### 17.2.5 BinocularCameraFrame

Binocular camera frame data structure, containing format and image frames.

Field Name	Type	Description
header	Header	Common message header (timestamp + frame_id)
format	str	Image format
data	list[uint8_t]	Left and right eye stitched image data, left half is left eye image, right half is right eye image

## 17.3 Notice:

When using subscription-type SDK interfaces such as `Subscribe`, do not perform blocking operations within the callback function. Doing so may cause message congestion, processing delays, or even unexpected errors.

---

## Audio Control Service (Python)

---

---

Provides robot system audio service controller. Through the `AudioController`, you can control robot audio and obtain status via RPC methods.

### 18.1 Interface Definition

`AudioController` is a Python class that encapsulates audio control functionality, mainly used for audio playback control, TTS playback, volume setting and query, etc.

#### 18.1.1 `AudioController`

Item	Content
Class Name	<code>AudioController</code>
Constructor	<code>controller = AudioController()</code>
Function Overview	Initialize audio controller object, construct internal state, allocate resources, etc.
Notes	Constructs internal state.

## 18.1.2 initialize

Item	Content
Function Name	<code>initialize</code>
Function Declaration	<code>bool initialize()</code>
Function Overview	Initialize audio control module, prepare playback resources and devices.
Return Value	<code>True</code> indicates success, <code>False</code> indicates failure.
Notes	Used in conjunction with <code>shutdown()</code> .

## 18.1.3 shutdown

Item	Content
Function Name	<code>shutdown</code>
Function Declaration	<code>void shutdown()</code>
Function Overview	Shutdown audio controller and release resources.
Notes	Ensure to call before destruction.

## 18.1.4 play

Item	Content
Function Name	<code>play</code>
Function Declaration	<code>Status play(TtsCommand cmd, int timeout_ms)</code>
Function Overview	Play TTS (Text-to-Speech) audio command.
Parameter Description	<code>cmd</code> : TTS command, containing text, speech rate, tone, etc.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, ensure module is initialized before calling.

## 18.1.5 stop

Item	Content
Function Name	<code>stop</code>
Function Declaration	<code>Status stop()</code>
Function Overview	Stop current audio playback.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, usually used to interrupt current speech.

### 18.1.6 set\_volume

Item	Content
Function Name	<code>set_volume</code>
Function Declaration	<code>Status set_volume(int volume)</code>
Function Overview	Set audio output volume.
Parameter Description	<code>volume</code> : Volume value, usually in range 0~100.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, takes effect immediately after setting.

### 18.1.7 get\_volume

Item	Content
Function Name	<code>get_volume</code>
Function Declaration	<code>tuple[Status, int] get_volume()</code>
Function Overview	Get current audio output volume.
Return Value	Returns tuple ( <code>Status</code> , <code>volume</code> ), <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, return value needs to be checked before using <code>volume</code> .

### 18.1.8 open\_audio\_stream

Item	Content
Function Name	<code>open_audio_stream</code>
Function Declaration	<code>Status open_audio_stream()</code>
Function Overview	Open audio stream, prepare for audio playback.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, return value needs to be checked for successful execution

### 18.1.9 close\_audio\_stream

Item	Content
Function Name	<code>close_audio_stream</code>
Function Declaration	<code>Status close_audio_stream()</code>
Function Overview	Close audio stream.
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success.
Notes	Blocking interface, return value needs to be checked for successful execution

### 18.1.10 subscribe\_origin\_audio\_stream

Item	Content
Function Name	subscribe_origin_audio_stream
Function Declaration	void subscribe_origin_audio_stream(callback)
Function Overview	Subscribe to original audio stream data.
Parameter Description	callback: Data processing function after receiving data, signature is callback(data: AudioStream) -> None
Notes	Non-blocking interface.

### 18.1.11 subscribe\_bf\_audio\_stream

Item	Content
Function Name	subscribe_bf_audio_stream
Function Declaration	void subscribe_bf_audio_stream(callback)
Function Overview	Subscribe to BF audio stream data.
Parameter Description	callback: Data processing function after receiving data, signature is callback(data: AudioStream) -> None
Notes	Non-blocking interface.

### 18.1.12 unsubscribe\_origin\_audio\_stream

Item	Content
Function Name	unsubscribe_origin_audio_stream
Function Declaration	void unsubscribe_origin_audio_stream()
Function Overview	Unsubscribe from original audio stream data
Remarks	Non-blocking interface, used in pair with subscribe_origin_audio_stream.

### 18.1.13 unsubscribe\_bf\_audio\_stream

Item	Content
Function Name	unsubscribe_bf_audio_stream
Function Declaration	void unsubscribe_bf_audio_stream()
Function Overview	Unsubscribe from BF audio stream data
Remarks	Non-blocking interface, used in pair with subscribe_bf_audio_stream.



### 18.1.14 open\_wakeup\_status\_stream

Item	Content
Function Name	<code>open_wakeup_status_stream</code>
Function Declaration	<code>Status open_wakeup_status_stream()</code>
Function Overview	Enable voice wake-up status stream
Return Value	Operation status, returns Status.OK on success

### 18.1.15 close\_wakeup\_status\_stream

Item	Content
Function Name	<code>close_wakeup_status_stream</code>
Function Declaration	<code>Status close_wakeup_status_stream()</code>
Function Overview	Disable voice wake-up status stream
Return Value	Operation status, returns Status.OK on success

### 18.1.16 subscribe\_wakeup\_status

Item	Content
Function Name	<code>subscribe_wakeup_status</code>
Function Declaration	<code>void subscribe_wakeup_status(callback)</code>
Function Overview	Subscribe to voice wake-up status
Parameter Description	callback: Callback function for processing wake-up status when received

### 18.1.17 unsubscribe\_wakeup\_status

Item	Content
Function Name	<code>unsubscribe_wakeup_status</code>
Function Declaration	<code>void unsubscribe_wakeup_status()</code>
Function Overview	Unsubscribe from voice wake-up status

## 18.2 Type Definitions

### 18.2.1 TtsPriority —TTS Playback Priority Level

Used to control interrupt behavior between different TTS tasks. Higher priority tasks will interrupt playback of current lower priority tasks.

Enumeration Value	Description
<code>TtsPriority.HIGH</code>	Highest priority, e.g.: low battery warning, emergency alert
<code>TtsPriority.MIDDLE</code>	Medium priority, e.g.: system prompts, status announcements
<code>TtsPriority.LOW</code>	Lowest priority, e.g.: daily voice conversation, background announcements

## 18.2.2 `TtsMode` —Task Scheduling Strategy Under Same Priority

Used to refine control of playback order and clearing logic for multiple TTS tasks under the same priority condition.

Enumeration Value	Description
<code>TtsMode.CLEARTOP</code>	Clear all tasks of current priority (including currently playing and waiting queue), immediately play this request
<code>TtsMode.ADD</code>	Append this request to the end of current priority queue, play in order (without interrupting current playback)
<code>TtsMode.CLEARBUFFER</code>	Clear unplayed requests in queue, keep current playback, then play this request

## 18.3 Structure Definitions

### 18.3.1 `TtsCommand` —TTS Playback Command Structure

Describes complete information for a TTS playback request, supporting setting unique identifier, text content, priority control, and scheduling mode under same priority.


Field Name	Type	Description
<code>id</code>	<code>str</code>	TTS task unique ID, e.g. <code>"id_01"</code> , used to track playback status
<code>content</code>	<code>str</code>	Text content to be played, e.g. <code>"Hello, welcome to the intelligent voice system."</code>
<code>priority</code>	<code>TtsPriority</code>	Playback priority, controls whether to interrupt currently playing low-priority speech
<code>mode</code>	<code>TtsMode</code>	Scheduling strategy under same priority, controls whether tasks are appended, overridden, etc.

### 18.3.2 AudioStream - Audio Stream Structure

Describes raw audio stream or BF audio stream data.

Field Name	Type	Description
data_length	int	Data length
raw_data	bytes	Audio stream data

## 18.4 DOA



## 18.5 Notice:

When using subscription-type SDK interfaces such as `Subscribe`, do not perform blocking operations within the callback function. Doing so may cause message congestion, processing delays, or even unexpected errors.

---

## State Monitor Service (Python)

---

---

Provides robot state monitoring interface class. Through the `StateMonitor`, you can provide state query and other interfaces.

### 19.1 Interface Definition

`StateMonitor` is a robot system state monitoring management class, typically used to control robot state management, supporting state queries.

#### 19.1.1 `StateMonitor`

Item	Content
Function Name	<code>StateMonitor</code>
Function Declaration	<code>StateMonitor()</code> ;
Function Overview	Constructor, initializes state monitor object.
Notes	Constructs internal state.

### 19.1.2 ~StateMonitor

Item	Content
Function Name	<code>~StateMonitor</code>
Function Declaration	<code>virtual ~StateMonitor();</code>
Function Overview	Destructor, releases resources.
Notes	Sensors should be closed before calling.

### 19.1.3 Initialize

Item	Content
Function Name	<code>Initialize</code>
Function Declaration	<code>bool Initialize();</code>
Function Overview	Initialize controller, including resource allocation and driver loading.
Return Value	<code>true</code> indicates success, <code>false</code> indicates failure.
Notes	Object must be constructed before calling.

### 19.1.4 Shutdown

Item	Content
Function Name	<code>Shutdown</code>
Function Declaration	<code>void Shutdown();</code>
Function Overview	Shutdown and release resources.
Notes	Used in conjunction with <code>Initialize</code> .

### 19.1.5 get\_current\_state

Item	Content
Function Name	<code>get_current_state</code>
Function Declaration	<code>RobotState get_current_state()</code>
Function Overview	Get current robot aggregated state
Return Value	<code>tuple[Status, RobotState]</code> object
Notes	Non-blocking interface, gets recently monitored robot state data, including BMS/fault state monitoring, etc., will be iteratively expanded in the future

### 19.1.6 RobotState —Robot State Data Structure

Used to represent overall robot state information:

Field Name	Type	Description
faults	list[Fault]	Fault information list
bms_data	BmsData	Battery Management System data

### 19.1.7 BmsData —Battery Management System Data Structure

Represents battery state information:

Field Name	Type	Description
battery_percentage	float	Current battery remaining power (percentage, 0~100)
battery_health	float	Battery health status (higher is better)
battery_state	BatteryState	Battery state (see enumeration below)
power_supply_status	PowerSupplyStatus	Battery charge/discharge state (see enumeration below)

### 19.1.8 Enumeration Type Definitions

#### BatteryState —Battery State Enumeration Type

Used to represent the current state of the battery, used for battery state judgment and processing in the system:

Enumeration Value	Value	Description
BatteryState.UNKNOWN	0	Unknown state
BatteryState.GOOD	1	Battery state good
BatteryState.OVERHEAT	2	Battery overheating
BatteryState.DEAD	3	Battery damaged
BatteryState.OVERVOLTAGE	4	Battery overvoltage
BatteryState.UNSPEC_FAILURE	5	Unknown fault
BatteryState.COLD	6	Battery overcooled
BatteryState.WATCHDOG_TIMER_EXPIRE	7	Watchdog timer timeout
BatteryState.SAFETY_TIMER_EXPIRE	8	Safety timer timeout

#### PowerSupplyStatus —Battery Charge/Discharge State

Used to represent the current battery charge/discharge state:

Enumeration Value	Value	Description
PowerSupplyStatus.UNKNOWN	0	Unknown state
PowerSupplyStatus.CHARGING	1	Battery charging
PowerSupplyStatus.DISCHARGING	2	Battery discharging
PowerSupplyStatus.NOTCHARGING	3	Battery not charging/discharging
PowerSupplyStatus.FULL	4	Battery fully charged

## 19.2 Error Code Mapping Table

Error Code (Hexadecimal)	Error Description
0x0000	No fault
0x1101	Service invocation failed
0x1301	Central control node lost
0x1302	App node lost
0x1303	Audio node lost
0x1304	Stereo camera node lost
0x1305	LIDAR node lost
0x1306	SLAM node lost
0x1307	Navigation node lost
0x1308	AI node lost
0x1309	Head node lost
0x130A	Point cloud node lost
0x2201	No LIDAR data received
0x2202	No stereo camera data received
0x2203	Stereo camera data error
0x2204	Stereo camera initialization failed
0x220B	No odometry data received
0x220C	No IMU data received
0x2215	Depth camera not detected
0x3101	Failed to connect robot to app
0x3102	Heartbeat lost - assertion failed
0x4201	Failed to open head serial port
0x4202	No head data received
0x5201	No navigation TF data
0x5202	No navigation map data
0x5203	No navigation localization data
0x5204	No navigation LIDAR data

continues on next page



Table 1 – continued from previous page

Error Code (Hexadecimal)	Error Description
0x5205	No navigation depth camera data
0x5206	No navigation multi-line LIDAR data
0x5207	No navigation odometry data
0x6201	SLAM localization error
0x6102	No SLAM LIDAR data
0x6103	No SLAM odometry data
0x6104	SLAM map data error
0x7201	LCM connection timeout
0x8201	Left leg hardware error
0x8202	Right leg hardware error
0x8203	Left arm hardware error
0x8204	Right arm hardware error
0x8205	Waist hardware error
0x8206	Head hardware error
0x8207	Hand hardware error
0x8208	Gripper hardware error
0x8209	IMU hardware error
0x820A	Power system hardware error
0x820B	Leg force sensor hardware error
0x820C	Arm force sensor hardware error
0x9201	ECAT (EtherCAT) hardware error
0xA201	Motion posture error
0xA202	Foot position deviation during movement
0xA203	Joint velocity error during motion



---

## SLAM Navigation Control Service (Python)

---

Provides SLAM (Simultaneous Localization and Mapping) and navigation control services for robot systems. Through `SlamNavController`, RPC communication can be used to control robot mapping, localization, navigation and other functions.

### 20.1 Interface Definition

`SlamNavController` is a controller for SLAM and navigation control, supporting control operations such as mapping, localization, navigation, and map management, encapsulating underlying details for upper-level system calls.

#### 20.1.1 SlamNavController

Item	Content
Class Name	<code>SlamNavController</code>
Class Declaration	<code>SlamNavController()</code>
Function Overview	Constructor, initializes SLAM navigation controller state
Remarks	Constructs internal control resources

## 20.1.2 initialize

Item	Content
Method Name	<code>initialize</code>
Method Declaration	<code>bool initialize()</code>
Function Overview	Initializes SLAM navigation controller, prepares SLAM and navigation functions
Return Value	<code>True</code> indicates success, <code>False</code> indicates failure
Remarks	Must be called before first use

## 20.1.3 shutdown

Item	Content
Method Name	<code>shutdown</code>
Method Declaration	<code>void shutdown()</code>
Function Overview	Closes controller and releases resources
Remarks	Used in conjunction with <code>initialize</code> , safely disconnects

## 20.1.4 activate\_slam\_mode

Item	Content
Method Name	<code>activate_slam_mode</code>
Method Declaration	<code>Status activate_slam_mode(SlamMode mode, str map_path = "", int timeout_ms)</code>
Function Overview	Activates SLAM mode and starts mapping or localization mode
Parameter Description	<code>mode</code> : SLAM mode enumeration <code>map_path</code> : Map path (used in localization mode), can be obtained through <code>get_map_path</code> <code>timeout_ms</code> : Timeout time (milliseconds), default value is 10000
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, supports mapping and localization mode switching

### 20.1.5 start\_mapping

Item	Content
Method Name	start_mapping
Method Declaration	Status start_mapping(int timeout_ms)
Function Overview	Starts mapping
Parameter Description	timeout_ms: Timeout time (milliseconds), default value is 10000
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, mapping mode must be activated first

### 20.1.6 cancel\_mapping

Item	Content
Method Name	cancel_mapping
Method Declaration	Status cancel_mapping(int timeout_ms)
Function Overview	Cancels mapping
Parameter Description	timeout_ms: Timeout time (milliseconds), default value is 10000
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, cancels current mapping task

### 20.1.7 save\_map

Item	Content
Method Name	save_map
Method Declaration	Status save_map(str map_name, int timeout_ms)
Function Overview	Ends mapping and saves the map
Parameter Description	map_name: Map name timeout_ms: Timeout time (milliseconds), default value is 10000
Return Value	Status::OK indicates success, others indicate failure
Remarks	Blocking interface, must be called in mapping mode

## 20.1.8 load\_map

Item	Content
Method Name	<code>load_map</code>
Method Declaration	<code>Status load_map(str map_name, int timeout_ms)</code>
Function Overview	Loads map and sets it as current map
Parameter Description	<code>map_name</code> : Map name <code>timeout_ms</code> : Timeout time (milliseconds), default value is 10000
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, loads map with specified name

## 20.1.9 delete\_map

Item	Content
Method Name	<code>delete_map</code>
Method Declaration	<code>Status delete_map(str map_name, int timeout_ms)</code>
Function Overview	Deletes map
Parameter Description	<code>map_name</code> : Name of map to delete <code>timeout_ms</code> : Timeout time (milliseconds), default value is 10000
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, permanently deletes specified map

## 20.1.10 get\_map\_path

Item	Content
Method Name	<code>get_map_path</code>
Method Declaration	<code>tuple[Status, List[str]] get_map_path(str map_name, int timeout_ms)</code>
Function Overview	Get map path
Parameter Description	<code>map_name</code> : Map name <code>timeout_ms</code> : Timeout time (milliseconds), default value is 10000
Return Value	<code>Status::OK</code> indicates success, others indicate failure <code>List[str]</code> : Map path (output parameter)
Remarks	Blocking interface, gets the storage path of the specified map

### 20.1.11 get\_all\_map\_info

Item	Content
Method Name	get_all_map_info
Method Declaration	<code>tuple[Status, AllMapInfo] get_all_map_info(int timeout_ms)</code>
Function Overview	Get all map information
Parameter Description	<code>timeout_ms</code> : Timeout time (milliseconds), default value is 10000
Return Value	<code>Status::OK</code> : indicates success, others indicate failure <code>AllMapInfo</code> : All map information (output parameter)
Remarks	Blocking interface, gets detailed information of all maps in the system

### 20.1.12 init\_pose

Item	Content
Method Name	init_pose
Method Declaration	<code>Status init_pose(Pose3DEuler pose, int timeout_ms)</code>
Function Overview	Initializes pose
Parameter Description	<code>pose</code> : Pose information to publish <code>timeout_ms</code> : Timeout time (milliseconds), default value is 15000
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, sets robot initial pose; when publishing pose, a fixed -1.57rad offset needs to be applied to the Yaw direction because there is a -1.57rad offset between the mechanical installation of the LiDAR and the robot body

### 20.1.13 get\_current\_localization\_info

Item	Content
Method Name	<code>get_current_localization_info</code>
Method Declaration	<code>Status get_current_localization_info(LocalizationInfo pose_info, int timeout_ms)</code>
Function Overview	Gets current pose information
Parameter Description	<code>pose_info</code> : Current position and orientation information (output parameter) <code>timeout_ms</code> : Timeout time (milliseconds), default value is 10000
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, gets robot current pose status

### 20.1.14 activate\_nav\_mode

Item	Content
Method Name	<code>activate_nav_mode</code>
Method Declaration	<code>Status activate_nav_mode(NavMode mode, str map_path = "", int timeout_ms)</code>
Function Overview	Activates navigation mode
Parameter Description	<code>mode</code> : Target navigation mode <code>map_path</code> : Map path (used in grid map mode), can be obtained through <code>get_map_path</code> <code>timeout_ms</code> : Timeout time (milliseconds), default value is 10000
Return Value	<code>Status::OK</code> indicates success, others indicate failure
Remarks	Blocking interface, activates specified navigation mode



### 20.1.15 set\_nav\_target

Item	Content
Method Name	set_nav_target
Method Declaration	Status set_nav_target (NavTarget goal, int timeout_ms)
Function Overview	Sets global navigation target point and starts navigation task
Parameter Description	goal: Global coordinates of target point timeout_ms: Timeout time (milliseconds), default value is 10000
Return Value	Status: :OK indicates success, others indicate failure
Remarks	Blocking interface, sets navigation target and starts navigation

### 20.1.16 pause\_nav\_task

Item	Content
Method Name	pause_nav_task
Method Declaration	Status pause_nav_task ()
Function Overview	Pauses current navigation task
Return Value	Status: :OK indicates success, others indicate failure
Remarks	Non-blocking interface, pauses navigation task

### 20.1.17 resume\_nav\_task

Item	Content
Method Name	resume_nav_task
Method Declaration	Status resume_nav_task ()
Function Overview	Resumes paused navigation task
Return Value	Status: :OK indicates success, others indicate failure
Remarks	Non-blocking interface, resumes paused navigation task

### 20.1.18 cancel\_nav\_task

Item	Content
Method Name	<code>cancel_nav_task</code>
Method Declaration	<code>Status cancel_nav_task()</code>
Function Overview	Cancels current navigation task
Return Value	<code>Status</code> : <code>:OK</code> indicates success, others indicate failure
Remarks	Non-blocking interface, cancels current navigation task

### 20.1.19 get\_nav\_task\_status

Item	Content
Method Name	<code>get_nav_task_status</code>
Method Declaration	<code>tuple[Status, NavStatus] get_nav_task_status()</code>
Function Overview	Retrieves the current status information of the navigation task.
Return Value	<code>Status</code> : <code>:OK</code> indicates success; others indicate failure. Returns a <code>NavStatus</code> object (empty on failure).
Remarks	This is a blocking interface for querying the navigation task status. Returns a <code>Status</code> code along with a <code>NavStatus</code> object, which can be used to check navigation progress and status.

### 20.1.20 open\_odometry\_stream

Item	Content
Function Name	<code>open_odometry_stream</code>
Function Declaration	<code>Status open_odometry_stream()</code>
Function Overview	Open odometry stream
Return Value	<code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success
Remarks	Blocking interface, check return value to ensure successful execution

### 20.1.21 close\_odometry\_stream

Item	Content
Function Name	close_odometry_stream
Function Declaration	Status close_odometry_stream()
Function Overview	Close odometry stream
Return Value	Status object, Status.code == ErrorCode.OK indicates success
Remarks	Blocking interface, used in conjunction with open_odometry_stream

### 20.1.22 subscribe\_odometry

Item	Content
Function Name	subscribe_odometry
Function Declaration	void subscribe_odometry(callback)
Function Overview	Subscribe to odometry data
Parameter Description	callback: Processing function after receiving odometry data, signature is callback(data: Odometry) -> None
Remarks	Non-blocking interface, callback function will be called when odometry data is updated

### 20.1.23 unsubscribe\_odometry

Item	Content
Function Name	unsubscribe_odometry
Function Declaration	void unsubscribe_odometry()
Function Overview	Unsubscribe from odometry data
Remarks	Non-blocking interface. Used in conjunction with subscribe_odometry

## 20.1.24 get\_point\_cloud\_map

Item	Content
Function Name	<code>get_point_cloud_map</code>
Function Declaration	<code>tuple[Status, PointCloud2] get_point_cloud_map(int timeout_ms)</code>
Function Overview	Get point cloud map data
Parameter Description	<code>timeout_ms</code> : Timeout duration (milliseconds)
Return Value	Returns a tuple, first element is a <code>Status</code> object, <code>Status.code == ErrorCode.OK</code> indicates success; second element is the point cloud map data
Remarks	Blocking interface, gets current point cloud map data

## 20.1.25 unsubscribe\_localization\_point\_cloud\_map

Item	Content
Function Name	<code>unsubscribe_localization_point_cloud_map</code>
Function Declaration	<code>void unsubscribe_localization_point_cloud_map()</code>
Function Overview	Unsubscribe from localization point cloud map data
Remarks	Non-blocking interface. Used in conjunction with <code>subscribe_localization_point_cloud_map</code>

## 20.2 Type Definitions

### 20.2.1 Pose3DEuler —3D Pose Structure

Field Name	Type	Description
<code>position</code>	<code>List[float]</code>	Position coordinates (x, y, z)
<code>orientation</code>	<code>List[float]</code>	Euler angles (roll, pitch, yaw)

## 20.2.2 NavTarget —Navigation Target Point Structure

Field Name	Type	Description
id	int	Target point ID
frame_id	str	Target point coordinate frame ID
goal	Pose3DEuler	Target point pose

## 20.2.3 LocalizationInfo —Pose Information Structure

Field Name	Type	Description
is_localization	bool	Whether localized
pose	Pose3DEuler	Current pose

## 20.2.4 NavStatus —Navigation Status Structure

Field Name	Type	Description
id	int	Target point ID, -1 indicates no target point
status	NavStatusType	Navigation status type
message	str	Navigation status message

## 20.2.5 PolyRegion —Polygon Region Structure

Field Name	Type	Description
points	List[Point2D]	Polygon vertex list

## 20.2.6 Point2D —2D Point Structure

Field Name	Type	Description
x	float	X coordinate
y	float	Y coordinate

## 20.3 Enumeration Type Definitions

### 20.3.1 `slamMode` —SLAM Mode Enumeration

Enum Value	Value	Description
IDLE	0	Idle mode
LOCALIZATION	1	Localization mode
MAPPING	2	Mapping mode

### 20.3.2 `NavMode` —Navigation Mode Enumeration

Enum Value	Value	Description
IDLE	0	Idle mode
GRID_MAP	1	Grid map navigation mode

### 20.3.3 `NavStatusType` —Navigation Status Type Enumeration

Enum Value	Value	Description
NONE	0	No status
RUNNING	1	Running
END_SUCCESS	2	Successfully ended
END_FAILED	3	Failed to end
PAUSE	4	Paused
CONTINUE	5	Continue
CANCEL	6	Canceled

## 20.4 SLAM Navigation Control Introduction

The robot's SLAM navigation control service can be divided into SLAM functions and navigation functions.

- In SLAM functions, corresponding interfaces can be called to implement mapping, localization, map management and other functions.
- In navigation functions, corresponding interfaces can be called to implement target navigation, navigation control and other functions.

## 20.4.1 Applicable Scenarios and Scope

- Static indoor flat areas smaller than 100 m × 100 m with rich features. Do not exceed the recommended range.
- This functionality is applicable to the education and research industry and is not recommended for commercial applications. For commercial use, please contact sales.

## 20.4.2 SLAM Function Flow

Function	Operation Flow
Mapping	Activate mapping mode → Start mapping → Save map
Map Management	Load map, get map information, delete map, get map path, etc.

## 20.4.3 Navigation Function Flow

Function	Operation Flow
Localization	Load map → Activate localization mode → Initialize pose → Get localization status
Navigation	Localization success → Activate navigation mode → Set target pose → Get navigation status
Navigation Control	Set target pose → PauseNavTask navigation → ResumeNavTask navigation → CancelNavTask navigation

## 20.4.4 Localization Mode Initialization

When SLAM is in localization mode, an initial pose can be specified to quickly complete relocalization and initialization. For large-scale maps, specifying the initial pose is mandatory.

### Small Map Mode

满足如下条件:

The following conditions must be met:

- Condition 1: The map should not be too large. For example, in a single room, it is best to keep the map area within 10m × 10m.
- Condition 2: Modify the configuration to adapt to this mode:

```
# Log in to the robot
ssh eame@192.168.54.119
# Modify the following configuration
# vim /opt/eame/eamegrapher_3d/share/eamegrapher_3d/config/params.yaml
reloc_options: true
```

(continues on next page)

(continued from previous page)

```
# After modifying the YAML file for the first time, restart the SLAM module for the_
↪change to take effect:
sudo systemctl restart slam.service
```

## Large Map Mode

The following conditions must be met:

- Condition 1: The robot must be located at the mapping origin (the starting position when mapping began), and the robot's orientation must remain consistent.
- Condition 2: Modify the configuration to adapt to this mode:

When using the SDK for SLAM navigation (unlike the app, which allows convenient visual positioning), you must modify the SLAM configuration to fix the map orientation and facilitate localization:

```
# Log in to the robot
ssh eame@192.168.54.119
# Modify the following configuration
# vim /opt/eame/eamegrapher_3d/share/eamegrapher_3d/config/params.yaml
align_map: false

# After modifying the YAML file for the first time, restart the SLAM module for the_
↪change to take effect:
sudo systemctl restart slam.service
```

- Condition 3: When initializing the pose, apply a 180° (3.14 rad) offset to the yaw angle:

because the LiDAR's mechanical installation differs from the robot body orientation by 180°.

### 20.4.5 Map Noise Removal and Obstacle Addition

- Software Name: GIMP
- Download Link: <https://www.gimp.org/downloads/>
- Operating System: Ubuntu
- File to Edit: /home/eame/cust\_para/maps/\${map\_name}/map/map.pgm Log in to the robot (ssh eame@192.168.54.119), open the .pgm map file with GIMP for editing, and replace the original file after modifications are complete.
- Editing Tutorial Video:



---

## High-Level Motion Control Example

---

This example demonstrates how to use the Magicbot-Z1 SDK for initialization, robot connection, high-level motion control (gait, tricks, remote control), and other basic operations.

### 21.1 C++:

Example file: `high_level_motion_example.cpp`

```
#include "magic_robot.h"
#include "magic_sdk_version.h"

#include <termios.h>
#include <unistd.h>
#include <csignal>

#include <iostream>

using namespace magic::z1;

magic::z1::MagicRobot robot;

void signalHandler(int signum) {
    std::cout << "Interrupt signal (" << signum << ") received.\n";
```

(continues on next page)

(continued from previous page)

```

robot.Shutdown();
// Exit process
exit(signum);
}

void print_help() {
    std::cout << "Key Function Demo Program\n\n";
    std::cout << "High-Level Motion Control Function Description:\n";
    std::cout << "  1      Function 1: Recovery stand\n";
    std::cout << "  2      Function 2: Balance stand\n";
    std::cout << "  3      Function 3: Execute trick - greeting action\n";
    std::cout << "  w      Function w: Move forward\n";
    std::cout << "  a      Function a: Move left\n";
    std::cout << "  s      Function s: Move backward\n";
    std::cout << "  d      Function d: Move right\n";
    std::cout << "  x      Function x: Stop moving\n";
    std::cout << "  t      Function t: Turn left\n";
    std::cout << "  g      Function g: Turn right\n";
    std::cout << "  u      Function u: Reset head move\n";
    std::cout << "  j      Function j: Move head left\n";
    std::cout << "  k      Function k: Move head right\n";
    std::cout << "\n";
    std::cout << "  ?      Function ?: Print help\n";
    std::cout << "  ESC    Exit program\n";
}

int getch() {
    struct termios oldt, newt;
    int ch;
    tcgetattr(STDIN_FILENO, &oldt); // Get current terminal settings
    newt = oldt;
    newt.c_lflag &= ~(ICANON | ECHO); // Disable buffering and echo
    tcsetattr(STDIN_FILENO, TCSANOW, &newt);
    ch = getchar(); // Read key press
    tcsetattr(STDIN_FILENO, TCSANOW, &oldt); // Restore settings
    return ch;
}

void RecoveryStand() {

```

(continues on next page)

(continued from previous page)

```
// Get high-level motion controller
auto& controller = robot.GetHighLevelMotionController();

// Set gait
auto status = controller.SetGait(GaitMode::GAIT_RECOVERY_STAND);
if (status.code != ErrorCode::OK) {
    std::cerr << "set robot gait failed"
                << ", code: " << status.code
                << ", message: " << status.message << std::endl;
    return;
}
}

void BalanceStand() {
    // Get high-level motion controller
    auto& controller = robot.GetHighLevelMotionController();

    // Set posture display gait
    auto status = controller.SetGait(GaitMode::GAIT_BALANCE_STAND);
    if (status.code != ErrorCode::OK) {
        std::cerr << "set robot gait failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }
    std::cout << "robot gait set to GAIT_BALANCE_STAND successfully." << std::endl;
}

void ExecuteTrick() {
    // Get high-level motion controller
    auto& controller = robot.GetHighLevelMotionController();

    // Execute trick
    auto status = controller.ExecuteTrick(TrickAction::ACTION_LEFT_GREETING);
    if (status.code != ErrorCode::OK) {
        std::cerr << "execute robot trick failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }
}
```

(continues on next page)

(continued from previous page)

```

    std::cout << "robot trick executed successfully." << std::endl;
}

void JoyStickCommand(float left_x_axis,
                    float left_y_axis,
                    float right_x_axis,
                    float right_y_axis) {
    // Get high-level motion controller
    auto& controller = robot.GetHighLevelMotionController();

    JoystickCommand joy_command;
    joy_command.left_x_axis = left_x_axis;
    joy_command.left_y_axis = left_y_axis;
    joy_command.right_x_axis = right_x_axis;
    joy_command.right_y_axis = right_y_axis;
    controller.SendJoyStickCommand(joy_command);
}

void HeadMove(float shake_angle) {
    // Get high-level motion controller
    auto& controller = robot.GetHighLevelMotionController();
    auto status = controller.HeadMove(shake_angle);
    if (status.code != ErrorCode::OK) {
        std::cerr << "head move failed"
                  << ", code: " << status.code
                  << ", message: " << status.message << std::endl;
        return;
    }
    std::cout << "head move successfully." << std::endl;
    std::cout << "shake_angle: " << shake_angle << std::endl;
}

int main(int argc, char* argv[]) {
    // Bind SIGINT (Ctrl+C)
    signal(SIGINT, signalHandler);

    std::cout << "SDK Version: " << SDK_VERSION_STRING << std::endl;

    print_help();
}

```

(continues on next page)

(continued from previous page)

```
std::string local_ip = "192.168.54.111";
// Configure local IP address for direct ethernet connection to robot and
↳ initialize SDK
if (!robot.Initialize(local_ip)) {
    std::cerr << "robot sdk initialize failed." << std::endl;
    robot.Shutdown();
    return -1;
}

// Connect to robot
auto status = robot.Connect();
if (status.code != ErrorCode::OK) {
    std::cerr << "connect robot failed"
                << ", code: " << status.code
                << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}

// Switch motion controller to high-level controller, default is high-level
↳ controller
status = robot.SetMotionControlLevel(ControllerLevel::HighLevel);
if (status.code != ErrorCode::OK) {
    std::cerr << "switch robot motion control level failed"
                << ", code: " << status.code
                << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}

std::cout << "Press any key to continue (ESC to exit)..."
          << std::endl;

// Wait for user input
while (1) {
    int key = getch();
    if (key == 27)
        break; // ESC key ASCII code is 27

    std::cout << "Key ASCII: " << key << ", Character: " << static_cast<char>(key) <<
```

(continues on next page)

(continued from previous page)

```

↪std::endl;

    switch (key) {
        case '1': {
            RecoveryStand();
            break;
        }
        case '2': {
            BalanceStand();
            break;
        }
        case '3': {
            ExecuteTrick();
            break;
        }
        case 'W':
        case 'w': {
            JoyStickCommand(0.0, 1.0, 0.0, 0.0); // Move forward
            break;
        }
        case 'A':
        case 'a': {
            JoyStickCommand(-1.0, 0.0, 0.0, 0.0); // Move left
            break;
        }
        case 'S':
        case 's': {
            JoyStickCommand(0.0, -1.0, 0.0, 0.0); // Move backward
            break;
        }
        case 'D':
        case 'd': {
            JoyStickCommand(1.0, 0.0, 0.0, 0.0); // Move right
            break;
        }
        case 'X':
        case 'x': {
            JoyStickCommand(0.0, 0.0, 0.0, 0.0); // Stop
            break;
        }
        case 'T':

```

(continues on next page)

(continued from previous page)

```

    case 't': {
        JoyStickCommand(0.0, 0.0, -1.0, 1.0); // Turn left
        break;
    }
    case 'G':
    case 'g': {
        JoyStickCommand(0.0, 0.0, 1.0, 1.0); // Turn right
        break;
    }
    case 'U':
    case 'u': {
        HeadMove(0.0);
        break;
    }
    case 'J':
    case 'j': {
        HeadMove(-0.5);
        break;
    }
    case 'K':
    case 'k': {
        HeadMove(0.5);
        break;
    }
    case '?': {
        print_help();
        break;
    }
    default:
        std::cout << "Unknown key: " << key << std::endl;
        break;
}

// Disconnect from robot
status = robot.Disconnect();
if (status.code != ErrorCode::OK) {
    std::cerr << "disconnect robot failed"
              << ", code: " << status.code
              << ", message: " << status.message << std::endl;
}

```

(continues on next page)

(continued from previous page)

```
robot.Shutdown();
    return -1;
}

robot.Shutdown();

return 0;
}
```

## 21.2 Python

Example file: high\_level\_motion\_example.py

```
#!/usr/bin/env python3

import sys
import time
import signal
import logging
from typing import Optional

import magicbot_z1_python as magicbot

# Configure logging format and level
logging.basicConfig(
    level=logging.INFO, # Minimum log level
    format="%(asctime)s [%(levelname)s] %(message)s",
    datefmt="%Y-%m-%d %H:%M:%S",
)

# Global variables
robot: Optional[magicbot.MagicRobot] = None
running = True

def signal_handler(signum, frame):
    """Signal handler function for graceful exit"""
    global running, robot
    logging.info("Received interrupt signal (%s), exiting...", signum)
    running = False
```

(continues on next page)



(continued from previous page)

```

if robot:
    robot.disconnect()
    logging.info("Robot disconnected")
    robot.shutdown()
    logging.info("Robot shutdown")
exit(-1)

def print_help():
    """Print help information"""
    logging.info("High-Level Motion Control Function Demo Program")
    logging.info("")
    logging.info("High-Level Motion Control Functions:")
    logging.info(" 1      Function 1: Recovery stand")
    logging.info(" 2      Function 2: Balance stand")
    logging.info(" 3      Function 3: Execute trick - welcome action")
    logging.info(" w      Function w: Move forward")
    logging.info(" a      Function a: Move left")
    logging.info(" s      Function s: Move backward")
    logging.info(" d      Function d: Move right")
    logging.info(" x      Function x: stop move")
    logging.info(" t      Function t: Turn left")
    logging.info(" g      Function g: Turn right")
    logging.info(" u      Function u: Reset head move")
    logging.info(" j      Function j: Move head left")
    logging.info(" k      Function k: Move head right")
    logging.info("")
    logging.info(" ?      Function ?: Print help")
    logging.info(" ESC    Exit program")

def get_user_input():
    """Get user input - 读取一行数据"""
    try:
        # 方法 1: 使用 input() 读取一行 (推荐)
        return input("请输入命令: ").strip()
    except (EOFError, KeyboardInterrupt):
        return ""

```

(continues on next page)

(continued from previous page)

```
def recovery_stand():
    """Recovery stand"""
    global robot
    try:
        logging.info("=== Executing Recovery Stand ===")

        # Get high-level motion controller
        controller = robot.get_high_level_motion_controller()

        # Set gait to recovery stand
        status = controller.set_gait(magicbot.GaitMode.GAIT_RECOVERY_STAND, 10000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to set robot gait, code: %s, message: %s",
                status.code,
                status.message,
            )
            return False

        logging.info("Robot gait set to recovery stand")
        return True

    except Exception as e:
        logging.error("Exception occurred while executing recovery stand: %s", e)
        return False

def balance_stand():
    """Balance stand"""
    global robot
    try:
        logging.info("=== Executing Balance Stand ===")

        # Get high-level motion controller
        controller = robot.get_high_level_motion_controller()

        # Set gait to balance stand
        status = controller.set_gait(magicbot.GaitMode.GAIT_BALANCE_STAND, 10000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
```

(continues on next page)

(continued from previous page)

```

        "Failed to set robot gait, code: %s, message: %s",
        status.code,
        status.message,
    )
    return False

    logging.info("Robot gait set to balance stand (supports movement)")
    return True

except Exception as e:
    logging.error("Exception occurred while executing balance stand: %s", e)
    return False

def get_action(cmd):
    if cmd == "215":
        return magicbot.TrickAction.ACTION_SHAKE_LEFT_HAND_REACHOUT
    elif cmd == "216":
        return magicbot.TrickAction.ACTION_SHAKE_LEFT_HAND_WITHDRAW
    elif cmd == "217":
        return magicbot.TrickAction.ACTION_SHAKE_RIGHT_HAND_REACHOUT
    elif cmd == "218":
        return magicbot.TrickAction.ACTION_SHAKE_RIGHT_HAND_WITHDRAW
    elif cmd == "220":
        return magicbot.TrickAction.ACTION_SHAKE_HEAD
    elif cmd == "300":
        return magicbot.TrickAction.ACTION_LEFT_GREETING
    elif cmd == "301":
        return magicbot.TrickAction.ACTION_RIGHT_GREETING
    elif cmd == "304":
        return magicbot.TrickAction.ACTION_TRUN_LEFT_INTRODUCE_HIGH
    elif cmd == "305":
        return magicbot.TrickAction.ACTION_TRUN_LEFT_INTRODUCE_LOW
    elif cmd == "306":
        return magicbot.TrickAction.ACTION_TRUN_RIGHT_INTRODUCE_HIGH
    elif cmd == "307":
        return magicbot.TrickAction.ACTION_TRUN_RIGHT_INTRODUCE_LOW
    elif cmd == "340":
        return magicbot.TrickAction.ACTION_WELCOME
    else:

```

(continues on next page)

(continued from previous page)

```

        return magicbot.TrickAction.ACTION_NONE

def execute_trick_action(cmd):
    """Execute trick - welcome action"""
    global robot
    try:
        logging.info("=== Executing Trick - %s Action ===", cmd)

        # Get high-level motion controller
        controller = robot.get_high_level_motion_controller()

        # Execute welcome trick
        status = controller.execute_trick(get_action(cmd), 10000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to execute robot trick, code: %s, message: %s",
                status.code,
                status.message,
            )
            return False

        logging.info("Robot trick executed successfully")
        return True

    except Exception as e:
        logging.error("Exception occurred while executing trick: %s", e)
        return False

def joystick_command(left_x_axis, left_y_axis, right_x_axis, right_y_axis):
    """Send joystick control command"""
    global robot
    try:
        # Get high-level motion controller
        controller = robot.get_high_level_motion_controller()

        # Create joystick command
        joy_command = magicbot.JoystickCommand()
        joy_command.left_x_axis = left_x_axis

```

(continues on next page)

(continued from previous page)

```

        joy_command.left_y_axis = left_y_axis
        joy_command.right_x_axis = right_x_axis
        joy_command.right_y_axis = right_y_axis

        # Send joystick command
        controller.send_joystick_command(joy_command)
    except Exception as e:
        logging.error("Exception occurred while sending joystick command: %s", e)

def move_forward():
    """Move forward"""
    logging.info("=== Moving Forward ===")
    return joystick_command(0.0, 1.0, 0.0, 0.0)

def move_backward():
    """Move backward"""
    logging.info("=== Moving Backward ===")
    return joystick_command(0.0, -1.0, 0.0, 0.0)

def move_left():
    """Move left"""
    logging.info("=== Moving Left ===")
    return joystick_command(-1.0, 0.0, 0.0, 0.0)

def move_right():
    """Move right"""
    logging.info("=== Moving Right ===")
    return joystick_command(1.0, 0.0, 0.0, 0.0)

def turn_left():
    """Turn left"""
    logging.info("=== Turning Left ===")
    return joystick_command(0.0, 0.0, -1.0, 0.0)

```

(continues on next page)

(continued from previous page)

```
def turn_right():
    """Turn right"""
    logging.info("=== Turning Right ===")
    return joystick_command(0.0, 0.0, 1.0, 0.0)

def stop_move():
    """Stop move"""
    logging.info("=== Stopping Move ===")
    return joystick_command(0.0, 0.0, 0.0, 0.0)

def head_move_reset():
    """Reset head move"""
    logging.info("=== Resetting Head Move ===")
    return head_move(0.0)

def head_move_left():
    """Move head left"""
    logging.info("=== Moving Head Left ===")
    return head_move(-0.5)

def head_move_right():
    """Move head right"""
    logging.info("=== Moving Head Right ===")
    return head_move(0.5)

def main():
    """Main function"""
    global robot, running

    # Bind signal handler
    signal.signal(signal.SIGINT, signal_handler)

    logging.info("Robot model: %s", magicbot.get_robot_model())

    # Create robot instance
```

(continues on next page)

(continued from previous page)

```
robot = magicbot.MagicRobot()

try:
    # Configure local IP address for direct network connection and initialize SDK
    local_ip = "192.168.54.111"
    if not robot.initialize(local_ip):
        logging.error("Failed to initialize robot SDK")
        robot.shutdown()
        return -1

    # Connect to robot
    status = robot.connect()
    if status.code != magicbot.ErrorCode.OK:
        logging.error(
            "Failed to connect to robot, code: %s, message: %s",
            status.code,
            status.message,
        )
        robot.shutdown()
        return -1

    logging.info("Successfully connected to robot")

    # Switch motion control controller to high-level controller
    status = robot.set_motion_control_level(magicbot.ControllerLevel.HighLevel)
    if status.code != magicbot.ErrorCode.OK:
        logging.error(
            "Failed to switch robot motion control level, code: %s, message: %s",
            status.code,
            status.message,
        )
        robot.shutdown()
        return -1

    logging.info("Switched to high-level motion controller")

    # Initialize high-level motion controller
    controller = robot.get_high_level_motion_controller()
    if not controller.initialize():
        logging.error("Failed to initialize high-level motion controller")
```

(continues on next page)

(continued from previous page)

```

robot.disconnect()
robot.shutdown()
return -1

logging.info("Successfully initialized high-level motion controller")

print_help()
logging.info("Press any key to continue (ESC to exit)...")

# Main loop
while running:
    try:
        str_input = get_user_input()

        # 按空格分割输入参数
        parts = str_input.strip().split()

        if not parts:
            time.sleep(0.01) # Brief delay
            continue

        # 解析参数
        key = parts[0]
        args = parts[1:] if len(parts) > 1 else []
        if key == "\x1b": # ESC key
            break

        if key == "1":
            recovery_stand()
        elif key == "2":
            balance_stand()
        elif key == "3":
            cmd = args[0] if args else 340
            execute_trick_action(cmd)
        elif key.upper() == "W":
            move_forward()
        elif key.upper() == "A":
            move_left()
        elif key.upper() == "S":
            move_backward()

```

(continues on next page)



(continued from previous page)

```

        elif key.upper() == "D":
            move_right()
        elif key.upper() == "X":
            stop_move()
        elif key.upper() == "T":
            turn_left()
        elif key.upper() == "G":
            turn_right()
        elif key.upper() == "U":
            head_move_reset()
        elif key.upper() == "J":
            head_move_left()
        elif key.upper() == "K":
            head_move_right()
        elif key.upper() == "?":
            print_help()
        else:
            logging.info("Unknown key: %s", key)

    time.sleep(0.01)  # Brief delay

except KeyboardInterrupt:
    break
except Exception as e:
    logging.error("Exception occurred while processing user input: %s", e)

except Exception as e:
    logging.error("Exception occurred during program execution: %s", e)
    return -1

finally:
    # Clean up resources
    try:
        logging.info("Clean up resources")
        # Close high-level motion controller
        controller = robot.get_high_level_motion_controller()
        controller.shutdown()
        logging.info("High-level motion controller closed")

    # Disconnect

```

(continues on next page)

(continued from previous page)

```
robot.disconnect()
logging.info("Robot connection disconnected")

# Shutdown robot
robot.shutdown()
logging.info("Robot shutdown")

except Exception as e:
    logging.error("Exception occurred while cleaning up resources: %s", e)

if __name__ == "__main__":
    sys.exit(main())
```

## 21.3 Running Instructions

### 21.3.1 Environment Setup

```
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH
```

### 21.3.2 Run Example

```
# C++
./high_level_motion_example
# Python
python3 high_level_motion_example.py
```

### 21.3.3 Control Instructions

- 1: Recovery stand
- 2: Balance stand
- 3: Celebration action
- w/a/s/d/x: Forward/Left/Backward/Right/Stop movement
- t/g: Turn left/right
- j/k/u: Head left/right/reset
- ?: Print help information

Note: The humanoid robot must land on the ground in the `recovery stand` state. After landing, switch to `balance stand`, and only then can perform tricks or other actions.

### 21.3.4 Stop Program

- Press `ESC` to safely stop the program
- The program will automatically clean up all resources



---

## Low-Level Motion Control Example

---

This example demonstrates how to use the Magicbot-Z1 SDK for initialization, robot connection, low-level motion control (hands, arms, legs, waist, head), IMU sensor data reading, and other basic operations.

### 22.1 C++:

Example file: `low_level_motion_example.cpp`

```
#include "magic_robot.h"
#include "magic_sdk_version.h"

#include <unistd.h>
#include <csignal>

#include <iostream>

using namespace magic::z1;

magic::z1::MagicRobot robot;

std::atomic<bool> running(true);

void signalHandler(int signum) {
```

(continues on next page)

(continued from previous page)

```
std::cout << "Interrupt signal (" << signum << ") received.\n";

running = false;

robot.Shutdown();
// Exit process
exit(signum);
}

int main() {
    // Bind SIGINT (Ctrl+C)
    signal(SIGINT, signalHandler);

    std::cout << "SDK Version: " << SDK_VERSION_STRING << std::endl;

    std::string local_ip = "192.168.54.111";
    // Configure local IP address for direct ethernet connection to robot and
    ↪ initialize SDK
    if (!robot.Initialize(local_ip)) {
        std::cerr << "robot sdk initialize failed." << std::endl;
        robot.Shutdown();
        return -1;
    }

    // Connect to robot
    auto status = robot.Connect();
    if (status.code != ErrorCode::OK) {
        std::cerr << "connect robot failed"
            << ", code: " << status.code
            << ", message: " << status.message << std::endl;
        robot.Shutdown();
        return -1;
    }

    // Switch motion controller to low-level controller, default is high-level
    ↪ controller
    status = robot.SetMotionControlLevel(ControllerLevel::LowLevel);
    if (status.code != ErrorCode::OK) {
        std::cerr << "switch robot motion control level failed"
            << ", code: " << status.code
```

(continues on next page)

(continued from previous page)

```

        << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}

// Get low-level controller
auto& controller = robot.GetLowLevelMotionController();

// Subscribe to IMU data
controller.SubscribeBodyImu([](const std::shared_ptr<Imu> msg) {
    static int32_t count = 0;
    if (count++ % 1000 == 1) {
        std::cout << "+++++++ receive imu data." << std::endl;
        std::cout << "timestamp: " << msg->timestamp << std::endl;
        std::cout << "temperature: " << msg->temperature << std::endl;
        std::cout << "orientation: " << msg->orientation[0] << ", " << msg->
orientation[1] << ", " << msg->orientation[2] << ", " << msg->orientation[3] <<
std::endl;
        std::cout << "angular_velocity: " << msg->angular_velocity[0] << ", " << msg->
angular_velocity[1] << ", " << msg->angular_velocity[2] << std::endl;
        std::cout << "linear_acceleration: " << msg->linear_acceleration[0] << ", " <<
msg->linear_acceleration[1] << ", " << msg->linear_acceleration[2] << std::endl;
    }
    // TODO: handle imu data
});

// Subscribe to arm data
controller.SubscribeArmState([](const std::shared_ptr<JointState> msg) {
    static int32_t count = 0;
    if (count++ % 1000 == 1) {
        std::cout << "+++++++ receive arm joint data." << std::endl;
        std::cout << "timestamp: " << msg->timestamp << std::endl;
        std::cout << "pos: " << msg->joints[0].posH << ", " << msg->joints[0].posL <<
std::endl;
        std::cout << "vel: " << msg->joints[0].vel << std::endl;
        std::cout << "toq: " << msg->joints[0].toq << std::endl;
        std::cout << "current: " << msg->joints[0].current << std::endl;
        std::cout << "error_code: " << msg->joints[0].err_code << std::endl;
    }
    // TODO: handle arm joint data
});

```

(continues on next page)

(continued from previous page)

```
});

// Using arm joint control as an example:
// Subsequent joint control commands, joint operation mode is 1, indicating joint_
↳ is in position control mode
auto now = std::chrono::steady_clock::now();
while (running.load()) {
    // Left arm joints, refer to documentation:
    // Left or right arm joints 1-5 operation_mode needs to switch from mode 200 to_
↳ mode 4 (series PID mode) for command execution;

    JointCommand arm_command;
    arm_command.joints.resize(kArmJointNum);
    for (int ii = 0; ii < kArmJointNum; ii++) {
        // Set joint to ready state
        arm_command.joints[ii].operation_mode = 200;
        // TODO: Set target position, velocity, torque and gains
        arm_command.joints[ii].pos = 0.0;
        arm_command.joints[ii].vel = 0.0;
        arm_command.joints[ii].toq = 0.0;
        arm_command.joints[ii].kp = 0.0;
        arm_command.joints[ii].kd = 0.0;
    }
    // Publish control command
    controller.PublishArmCommand(arm_command);

    // Send control commands at 500Hz frequency (2ms)
    now += std::chrono::microseconds(2000);
    std::this_thread::sleep_until(now);
}

// Disconnect from robot
status = robot.Disconnect();
if (status.code != ErrorCode::OK) {
    std::cerr << "disconnect robot failed"
                << ", code: " << status.code
                << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}
```

(continues on next page)



(continued from previous page)

```
robot.Shutdown();

return 0;
}
```

## 22.2 Python

Example file: low\_level\_motion\_example.py

```
#!/usr/bin/env python3

import sys
import time
import signal
import logging
from typing import Optional

import magicbot_z1_python as magicbot

# Configure logging format and level
logging.basicConfig(
    level=logging.INFO, # Minimum log level
    format="%(asctime)s [%(levelname)s] %(message)s",
    datefmt="%Y-%m-%d %H:%M:%S",
)

# Global variables
robot: Optional[magicbot.MagicRobot] = None
running = True

body_imu_counter = 0
arm_state_counter = 0
leg_state_counter = 0
head_state_counter = 0
waist_state_counter = 0

def signal_handler(signum, frame):
    """Signal handler function for graceful exit"""
    global robot, running
```

(continues on next page)

(continued from previous page)

```

running = False
logging.info("Received interrupt signal (%s), exiting...", signum)

if robot:
    robot.disconnect()
    logging.info("Robot disconnected")
    robot.shutdown()
    logging.info("Robot shutdown")
exit(-1)

def body_imu_callback(imu_data):
    """Body IMU data callback function"""
    global body_imu_counter
    if body_imu_counter % 1000 == 0:
        logging.info("+++++++ Received body IMU data")
        # Print IMU data
        logging.info("Received body IMU data, timestamp: %d", imu_data.timestamp)
        logging.info("Received body IMU data, orientation: [%f,%f,%f,%f]", imu_data.
↪orientation[0], imu_data.orientation[1], imu_data.orientation[2], imu_data.
↪orientation[3])
        logging.info(
            "Received body IMU data, angular_velocity: [%f,%f,%f]",
            imu_data.angular_velocity[0],
            imu_data.angular_velocity[1],
            imu_data.angular_velocity[2],
        )
        logging.info(
            "Received body IMU data, linear_acceleration: [%f,%f,%f]",
            imu_data.linear_acceleration[0],
            imu_data.linear_acceleration[1],
            imu_data.linear_acceleration[2],
        )
        logging.info("Received body IMU data, temperature: %f", imu_data.temperature)
    body_imu_counter += 1

def arm_state_callback(joint_state):
    """Arm joint state callback function"""
    global arm_state_counter

```

(continues on next page)

(continued from previous page)

```

if arm_state_counter % 1000 == 0:
    logging.info("+++++++ Received arm joint state data")
    # Print joint state data
    logging.info(
        "Received arm joint state data, status_word: %d",
        joint_state.joints[0].status_word,
    )
    logging.info(
        "Received arm joint state data, posH: %f", joint_state.joints[0].posH
    )
    logging.info(
        "Received arm joint state data, posL: %f", joint_state.joints[0].posL
    )
    logging.info(
        "Received arm joint state data, vel: %f", joint_state.joints[0].vel
    )
    logging.info(
        "Received arm joint state data, toq: %f", joint_state.joints[0].toq
    )
    logging.info(
        "Received arm joint state data, current: %f", joint_state.joints[0].
↪current
    )
    logging.info(
        "Received arm joint state data, error_code: %d",
        joint_state.joints[0].err_code,
    )
    arm_state_counter += 1

def leg_state_callback(joint_state):
    """Leg joint state callback function"""
    global leg_state_counter
    if leg_state_counter % 1000 == 0:
        logging.info("+++++++ Received leg joint state data")
        # Print joint state data
        logging.info(
            "Received leg joint state data, status_word: %d",
            joint_state.joints[0].status_word,
        )

```

(continues on next page)

(continued from previous page)

```

logging.info(
    "Received leg joint state data, posH: %f", joint_state.joints[0].posH
)
logging.info(
    "Received leg joint state data, posL: %f", joint_state.joints[0].posL
)
logging.info(
    "Received leg joint state data, vel: %f", joint_state.joints[0].vel
)
logging.info(
    "Received leg joint state data, toq: %f", joint_state.joints[0].toq
)
logging.info(
    "Received leg joint state data, current: %f", joint_state.joints[0].
↪current
)
logging.info(
    "Received leg joint state data, error_code: %d",
    joint_state.joints[0].err_code,
)
leg_state_counter += 1

def head_state_callback(joint_state):
    """Head joint state callback function"""
    global head_state_counter
    if head_state_counter % 1000 == 0:
        logging.info("+++++++ Received head joint state data")
        # Print joint state data
        logging.info(
            "Received head joint state data, status_word: %d",
            joint_state.joints[0].status_word,
        )
        logging.info(
            "Received head joint state data, posH: %f", joint_state.joints[0].posH
        )
        logging.info(
            "Received head joint state data, posL: %f", joint_state.joints[0].posL
        )
        logging.info(

```

(continues on next page)

(continued from previous page)

```

        "Received head joint state data, vel: %f", joint_state.joints[0].vel
    )
    logging.info(
        "Received head joint state data, toq: %f", joint_state.joints[0].toq
    )
    logging.info(
        "Received head joint state data, current: %f", joint_state.joints[0].
↪current
    )
    logging.info(
        "Received head joint state data, error_code: %d",
        joint_state.joints[0].err_code,
    )
    head_state_counter += 1

def waist_state_callback(joint_state):
    """Waist joint state callback function"""
    global waist_state_counter
    if waist_state_counter % 1000 == 0:
        logging.info("+++++++ Received waist joint state data")
        # Print joint state data
        logging.info(
            "Received waist joint state data, status_word: %d",
            joint_state.joints[0].status_word,
        )
        logging.info(
            "Received waist joint state data, posH: %f", joint_state.joints[0].posH
        )
        logging.info(
            "Received waist joint state data, posL: %f", joint_state.joints[0].posL
        )
        logging.info(
            "Received waist joint state data, vel: %f", joint_state.joints[0].vel
        )
        logging.info(
            "Received waist joint state data, toq: %f", joint_state.joints[0].toq
        )
        logging.info(
            "Received waist joint state data, current: %f",

```

(continues on next page)

(continued from previous page)

```

        joint_state.joints[0].current,
    )
    logging.info(
        "Received waist joint state data, error_code: %d",
        joint_state.joints[0].err_code,
    )
    waist_state_counter += 1

def main():
    """Main function"""
    global robot

    # Bind signal handler
    signal.signal(signal.SIGINT, signal_handler)

    logging.info("Robot model: %s", magicbot.get_robot_model())

    # Create robot instance
    robot = magicbot.MagicRobot()

    try:
        # Configure local IP address for direct network connection and initialize SDK
        local_ip = "192.168.54.111"
        if not robot.initialize(local_ip):
            logging.error("Failed to initialize robot SDK")
            robot.shutdown()
            return -1

        # Connect to robot
        status = robot.connect()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to connect to robot, code: %s, message: %s",
                status.code,
                status.message,
            )
            robot.shutdown()
            return -1

```

(continues on next page)

(continued from previous page)

```

logging.info("Successfully connected to robot")

# Switch motion control controller to low-level controller, default is high-
↪level controller
status = robot.set_motion_control_level(magicbot.ControllerLevel.LowLevel)
if status.code != magicbot.ErrorCode.OK:
    logging.error(
        "Failed to switch robot motion control level, code: %s, message: %s",
        status.code,
        status.message,
    )
    robot.shutdown()
    return -1

logging.info("Switched to low-level motion controller")

# Get low-level motion controller
controller = robot.get_low_level_motion_controller()

# Subscribe to body IMU data
controller.subscribe_body_imu(body_imu_callback)
logging.info("Subscribed to body IMU data")

# Subscribe to arm joint state
controller.subscribe_arm_state(arm_state_callback)
logging.info("Subscribed to arm joint state")

# Subscribe to leg joint state
controller.subscribe_leg_state(leg_state_callback)
logging.info("Subscribed to leg joint state")

# Subscribe to head joint state
controller.subscribe_head_state(head_state_callback)
logging.info("Subscribed to head joint state")

# Subscribe to waist joint state
controller.subscribe_waist_state(waist_state_callback)
logging.info("Subscribed to waist joint state")

# Main loop

```

(continues on next page)

(continued from previous page)

```

interval = 0.002 # 2ms
next_t = time.perf_counter() + interval

global running
while running:
    # Create arm joint control command
    arm_command = magicbot.JointCommand()
    leg_command = magicbot.JointCommand()
    waist_command = magicbot.JointCommand()
    head_command = magicbot.JointCommand()

    # Set all joints to preparation state (operation mode 200)
    for i in range(magicbot.ARM_JOINT_NUM):
        joint = magicbot.SingleJointCommand()
        joint.operation_mode = 200 # Preparation state
        joint.pos = 0.0
        joint.vel = 0.0
        joint.toq = 0.0
        joint.kp = 0.0
        joint.kd = 0.0
        arm_command.joints.append(joint)

    for i in range(magicbot.LEG_JOINT_NUM):
        joint = magicbot.SingleJointCommand()
        joint.operation_mode = 200 # Preparation state
        joint.pos = 0.0
        joint.vel = 0.0
        joint.toq = 0.0
        joint.kp = 0.0
        joint.kd = 0.0
        leg_command.joints.append(joint)

    for i in range(magicbot.HEAD_JOINT_NUM):
        joint = magicbot.SingleJointCommand()
        joint.operation_mode = 200 # Preparation state
        joint.pos = 0.0
        joint.vel = 0.0
        joint.toq = 0.0
        joint.kp = 0.0
        joint.kd = 0.0

```

(continues on next page)



(continued from previous page)

```

        head_command.joints.append(joint)

    for i in range(magicbot.WAIST_JOINT_NUM):
        joint = magicbot.SingleJointCommand()
        joint.operation_mode = 200 # Preparation state
        joint.pos = 0.0
        joint.vel = 0.0
        joint.toq = 0.0
        joint.kp = 0.0
        joint.kd = 0.0
        waist_command.joints.append(joint)

    # Publish arm joint control command
    controller.publish_arm_command(arm_command)

    # Publish leg joint control command
    controller.publish_leg_command(leg_command)

    # Publish waist joint control command
    controller.publish_waist_command(waist_command)

    # Publish head joint control command
    controller.publish_head_command(head_command)

    next_t += interval
    sleep_time = next_t - time.perf_counter()
    if sleep_time > 0:
        time.sleep(sleep_time)

except Exception as e:
    logging.error("Exception occurred during program execution: %s", e)
    return -1

finally:
    # Clean up resources
    try:
        logging.info("Clean up resources")
        # Close low-level motion controller
        controller = robot.get_low_level_motion_controller()
        controller.shutdown()

```

(continues on next page)

(continued from previous page)

```
logging.info("Low-level motion controller closed")

# Disconnect
robot.disconnect()
logging.info("Robot connection disconnected")

# Shutdown robot
robot.shutdown()
logging.info("Robot shutdown")

except Exception as e:
    logging.error("Exception occurred while cleaning up resources: %s", e)

if __name__ == "__main__":
    sys.exit(main())
```

## 22.3 Running Instructions

### 22.3.1 Environment Setup

```
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH
```

### 22.3.2 Run Example

```
# C++
./low_level_motion_example

# Python
python3 low_level_motion_example.py
```

### 22.3.3 Stop Program

- Press `Ctrl+C` to safely stop the program
- The program will automatically clean up all resources

---

## Sensor Control Example

---

---

This example demonstrates how to use the Magicbot-Z1 SDK for initialization, robot connection, robot sensor control (LiDAR, RGBD camera, binocular camera), and other basic operations.

### 23.1 C++

Example file: `sensor_example.cpp`

```
#include "magic_robot.h"
#include "magic_sdk_version.h"
#include "magic_type.h"

#include <termios.h>
#include <unistd.h>
#include <csignal>

#include <atomic>
#include <iomanip>
#include <iostream>
#include <map>
#include <string>

using namespace magic::z1;
```

(continues on next page)

(continued from previous page)

```
// Global variables
magic::z1::MagicRobot robot;
std::atomic<bool> running(true);

// Counters for data reception
std::atomic<int> lidar_imu_counter(0);
std::atomic<int> lidar_pointcloud_counter(0);
std::atomic<int> head_rgb_color_counter(0);
std::atomic<int> head_rgb_depth_counter(0);
std::atomic<int> head_rgb_camera_info_counter(0);
std::atomic<int> binocular_image_counter(0);

void signalHandler(int signum) {
    std::cout << "\nInterrupt signal (" << signum << ") received.\n";
    running = false;
    robot.Shutdown();
    exit(signum);
}

/**
 * @class SensorManager
 * @brief Manages sensor subscriptions for MagicBot Z1
 */
class SensorManager {
public:
    explicit SensorManager(sensor::SensorController& controller)
        : sensor_controller_(controller) {
        // Initialize sensor states
        sensors_state_["lidar"] = false;
        sensors_state_["head_rgb_camera"] = false;
        sensors_state_["binocular_camera"] = false;

        // Initialize subscription states
        subscriptions_["lidar_imu"] = false;
        subscriptions_["lidar_point_cloud"] = false;
        subscriptions_["head_rgb_color_image"] = false;
        subscriptions_["head_rgb_depth_image"] = false;
        subscriptions_["head_rgb_camera_info"] = false;
        subscriptions_["binocular_image"] = false;
    }
};
```

(continues on next page)

(continued from previous page)

```

}

// === LiDAR Control ===
bool OpenLidar() {
    if (sensors_state_["lidar"]) {
        std::cout << "[WARN] LiDAR already opened" << std::endl;
        return true;
    }

    auto status = sensor_controller_.OpenLidar();
    if (status.code != ErrorCode::OK) {
        std::cerr << "[ERROR] Failed to open LiDAR: " << status.message << std::endl;
        return false;
    }

    sensors_state_["lidar"] = true;
    std::cout << "[INFO] ✓ LiDAR opened successfully" << std::endl;
    return true;
}

bool CloseLidar() {
    if (!sensors_state_["lidar"]) {
        std::cout << "[WARN] LiDAR already closed" << std::endl;
        return true;
    }

    auto status = sensor_controller_.CloseLidar();
    if (status.code != ErrorCode::OK) {
        std::cerr << "[ERROR] Failed to close LiDAR: " << status.message << std::endl;
        return false;
    }

    sensors_state_["lidar"] = false;
    std::cout << "[INFO] ✓ LiDAR closed" << std::endl;
    return true;
}

// === Head RGBD Camera Control ===
bool OpenHeadRgbDCamera() {
    if (sensors_state_["head_rgbd_camera"]) {

```

(continues on next page)

(continued from previous page)

```

        std::cout << "[WARN] Head RGBD camera already opened" << std::endl;
        return true;
    }

    auto status = sensor_controller_.OpenHeadRgbDcamera();
    if (status.code != ErrorCode::OK) {
        std::cerr << "[ERROR] Failed to open head RGBD camera: " << status.message <<
↪std::endl;
        return false;
    }

    sensors_state_["head_rgbd_camera"] = true;
    std::cout << "[INFO] ✓ Head RGBD camera opened" << std::endl;
    return true;
}

bool CloseHeadRgbDcamera() {
    if (!sensors_state_["head_rgbd_camera"]) {
        std::cout << "[WARN] Head RGBD camera already closed" << std::endl;
        return true;
    }

    auto status = sensor_controller_.CloseHeadRgbDcamera();
    if (status.code != ErrorCode::OK) {
        std::cerr << "[ERROR] Failed to close head RGBD camera: " << status.message <<
↪std::endl;
        return false;
    }

    sensors_state_["head_rgbd_camera"] = false;
    std::cout << "[INFO] ✓ Head RGBD camera closed" << std::endl;
    return true;
}

// === Binocular Camera Control ===
bool OpenBinocularCamera() {
    if (sensors_state_["binocular_camera"]) {
        std::cout << "[WARN] Binocular camera already opened" << std::endl;
        return true;
    }

```

(continues on next page)

(continued from previous page)

```

    auto status = sensor_controller_.OpenBinocularCamera();
    if (status.code != ErrorCode::OK) {
        std::cerr << "[ERROR] Failed to open binocular camera: " << status.message << "\n";
        std::endl;
        return false;
    }

    sensors_state_["binocular_camera"] = true;
    std::cout << "[INFO] ✓ Binocular camera opened" << std::endl;
    return true;
}

bool CloseBinocularCamera() {
    if (!sensors_state_["binocular_camera"]) {
        std::cout << "[WARN] Binocular camera already closed" << std::endl;
        return true;
    }

    auto status = sensor_controller_.CloseBinocularCamera();
    if (status.code != ErrorCode::OK) {
        std::cerr << "[ERROR] Failed to close binocular camera: " << status.message << "\n";
        std::endl;
        return false;
    }

    sensors_state_["binocular_camera"] = false;
    std::cout << "[INFO] ✓ Binocular camera closed" << std::endl;
    return true;
}

// === LiDAR Subscribe Methods ===
void ToggleLidarImuSubscription() {
    if (subscriptions_["lidar_imu"]) {
        sensor_controller_.UnsubscribeLidarImu();
        subscriptions_["lidar_imu"] = false;
        std::cout << "[INFO] ☐ LiDAR IMU unsubscribed" << std::endl;
    } else {
        sensor_controller_.SubscribeLidarImu([](const std::shared_ptr<Imu>& imu) {
            int count = ++lidar_imu_counter;

```

(continues on next page)

(continued from previous page)

```

    if (count % 100 == 0) {
        std::cout << "===== LiDAR IMU Data =====" << std::endl;
        std::cout << "Counter: " << count << std::endl;
        std::cout << "Timestamp: " << imu->timestamp << std::endl;
        std::cout << std::fixed << std::setprecision(4);
        std::cout << "Orientation (x,y,z,w): ["
            << imu->orientation[0] << ", "
            << imu->orientation[1] << ", "
            << imu->orientation[2] << ", "
            << imu->orientation[3] << "]" << std::endl;
        std::cout << "Angular velocity (x,y,z): ["
            << imu->angular_velocity[0] << ", "
            << imu->angular_velocity[1] << ", "
            << imu->angular_velocity[2] << "]" << std::endl;
        std::cout << "Linear acceleration (x,y,z): ["
            << imu->linear_acceleration[0] << ", "
            << imu->linear_acceleration[1] << ", "
            << imu->linear_acceleration[2] << "]" << std::endl;
        std::cout << std::setprecision(2);
        std::cout << "Temperature: " << imu->temperature << std::endl;
        std::cout << "===== " << std::endl;
    }
});
subscriptions_["lidar_imu"] = true;
std::cout << "[INFO] ✓ LiDAR IMU subscribed" << std::endl;
}
}

void ToggleLidarPointCloudSubscription() {
    if (subscriptions_["lidar_point_cloud"]) {
        sensor_controller_.UnsubscribeLidarPointCloud();
        subscriptions_["lidar_point_cloud"] = false;
        std::cout << "[INFO] ☒ LiDAR point cloud unsubscribed" << std::endl;
    } else {
        sensor_controller_.SubscribeLidarPointCloud([](const std::shared_ptr
↪<PointCloud2>& pointcloud) {
            int count = ++lidar_pointcloud_counter;
            if (count % 10 == 0) {
                std::cout << "===== LiDAR Point Cloud =====" << std::endl;
                std::cout << "Counter: " << count << std::endl;
            }
        });
    }
}

```

(continues on next page)



(continued from previous page)

```

        std::cout << "Data size: " << pointcloud->data.size() << " bytes" <<
↪std::endl;
        std::cout << "Width: " << pointcloud->width << std::endl;
        std::cout << "Height: " << pointcloud->height << std::endl;
        std::cout << "Is dense: " << (pointcloud->is_dense ? "true" : "false") <<
↪std::endl;
        std::cout << "Point step: " << pointcloud->point_step << std::endl;
        std::cout << "Row step: " << pointcloud->row_step << std::endl;
        std::cout << "Number of fields: " << pointcloud->fields.size() << std::endl;
        if (!pointcloud->fields.empty()) {
            std::cout << "First field name: " << pointcloud->fields[0].name <<
↪std::endl;
        }
        std::cout << "=====" << std::endl;
    }
});
subscriptions_["lidar_point_cloud"] = true;
std::cout << "[INFO] ✓ LiDAR point cloud subscribed" << std::endl;
}
}

// === Head RGBD Subscribe Methods ===
void ToggleHeadRgbColorImageSubscription() {
    if (subscriptions_["head_rgb_color_image"]) {
        sensor_controller_.UnsubscribeHeadRgbColorImage();
        subscriptions_["head_rgb_color_image"] = false;
        std::cout << "[INFO] ☒ Head RGBD color image unsubscribed" << std::endl;
    } else {
        sensor_controller_.SubscribeHeadRgbColorImage([] (const std::shared_ptr<Image>&
↪img) {
            int count = ++head_rgb_color_counter;
            if (count % 15 == 0) {
                std::cout << "===== Head RGBD Color Image =====" << std::endl;
                std::cout << "Counter: " << count << std::endl;
                std::cout << "Size: " << img->data.size() << " bytes" << std::endl;
                std::cout << "Resolution: " << img->width << "x" << img->height <<
↪std::endl;
                std::cout << "Encoding: " << img->encoding << std::endl;
                std::cout << "=====" << std::endl;
            }
        });
    }
}

```

(continues on next page)

(continued from previous page)

```

    });
    subscriptions_["head_rgbd_color_image"] = true;
    std::cout << "[INFO] ✓ Head RGBD color image subscribed" << std::endl;
}

}

void ToggleHeadRgbDepthImageSubscription() {
    if (subscriptions_["head_rgbd_depth_image"]) {
        sensor_controller_.UnsubscribeHeadRgbDepthImage();
        subscriptions_["head_rgbd_depth_image"] = false;
        std::cout << "[INFO] ☒ Head RGBD depth image unsubscribed" << std::endl;
    } else {
        sensor_controller_.SubscribeHeadRgbDepthImage([] (const std::shared_ptr<Image>&
→img) {
            int count = ++head_rgbd_depth_counter;
            if (count % 15 == 0) {
                std::cout << "===== Head RGBD Depth Image =====" << std::endl;
                std::cout << "Counter: " << count << std::endl;
                std::cout << "Size: " << img->data.size() << " bytes" << std::endl;
                std::cout << "Resolution: " << img->width << "x" << img->height <<
→std::endl;
                std::cout << "Encoding: " << img->encoding << std::endl;
                std::cout << "===== " << std::endl;
            }
        });
        subscriptions_["head_rgbd_depth_image"] = true;
        std::cout << "[INFO] ✓ Head RGBD depth image subscribed" << std::endl;
    }
}

void ToggleHeadRgbCameraInfoSubscription() {
    if (subscriptions_["head_rgbd_camera_info"]) {
        sensor_controller_.UnsubscribeHeadRgbCameraInfo();
        subscriptions_["head_rgbd_camera_info"] = false;
        std::cout << "[INFO] ☒ Head RGBD camera info unsubscribed" << std::endl;
    } else {
        sensor_controller_.SubscribeHeadRgbCameraInfo([] (const std::shared_ptr
→<CameraInfo>& info) {
            int count = ++head_rgbd_camera_info_counter;
            if (count % 30 == 0) {

```

(continues on next page)

(continued from previous page)

```

        std::cout << "===== Head RGBD Camera Info =====" << std::endl;
        std::cout << "Counter: " << count << std::endl;
        std::cout << "Resolution: " << info->width << "x" << info->height <<
↪std::endl;

        std::cout << "Distortion model: " << info->distortion_model << std::endl;
        std::cout << "===== " << std::endl;
    }
});
subscriptions_["head_rgbd_camera_info"] = true;
std::cout << "[INFO] ✓ Head RGBD camera info subscribed" << std::endl;
}
}

// === Binocular Camera Subscribe Methods ===
void ToggleBinocularImageSubscription() {
    if (subscriptions_["binocular_image"]) {
        sensor_controller_.UnsubscribeBinocularImage();
        subscriptions_["binocular_image"] = false;
        std::cout << "[INFO] ☒ Binocular image unsubscribed" << std::endl;
    } else {
        sensor_controller_.SubscribeBinocularImage([](const std::shared_ptr
↪BinocularCameraFrame>& frame) {
            int count = ++binocular_image_counter;
            if (count % 15 == 0) {
                std::cout << "===== Binocular Camera Image =====" << std::endl;
                std::cout << "Counter: " << count << std::endl;
                std::cout << "Timestamp: " << frame->header.stamp << std::endl;
                std::cout << "Frame ID: " << frame->header.frame_id << std::endl;
                std::cout << "Format: " << frame->format << std::endl;
                std::cout << "Data size: " << frame->data.size() << " bytes (left+right_
↪concatenated)" << std::endl;
                std::cout << "===== " << std::endl;
            }
        });
        subscriptions_["binocular_image"] = true;
        std::cout << "[INFO] ✓ Binocular image subscribed" << std::endl;
    }
}

void ShowStatus() const {

```

(continues on next page)

(continued from previous page)

```
std::cout << "\n"
    << std::string(80, '=') << std::endl;
std::cout << "MAGICBOT Z1 SENSOR STATUS" << std::endl;
std::cout << std::string(80, '=') << std::endl;
std::cout << "LiDAR:                "
    << (sensors_state_.at("lidar") ? "OPEN" : "CLOSED") << std::endl;
std::cout << "Head RGBD Camera:            "
    << (sensors_state_.at("head_rgbd_camera") ? "OPEN" : "CLOSED") <<
↳std::endl;
std::cout << "Binocular Camera:          "
    << (sensors_state_.at("binocular_camera") ? "OPEN" : "CLOSED") <<
↳std::endl;

std::cout << "\nLiDAR SUBSCRIPTIONS:" << std::endl;
std::cout << "  LiDAR IMU:                "
    << (subscriptions_.at("lidar_imu") ? "✓ SUBSCRIBED" : "❌ UNSUBSCRIBED")
↳<< std::endl;
std::cout << "  LiDAR Point Cloud:          "
    << (subscriptions_.at("lidar_point_cloud") ? "✓ SUBSCRIBED" : "❌
↳UNSUBSCRIBED") << std::endl;

std::cout << "\nHEAD RGBD SUBSCRIPTIONS:" << std::endl;
std::cout << "  Color Image:                "
    << (subscriptions_.at("head_rgbd_color_image") ? "✓ SUBSCRIBED" : "❌
↳UNSUBSCRIBED") << std::endl;
std::cout << "  Depth Image:                "
    << (subscriptions_.at("head_rgbd_depth_image") ? "✓ SUBSCRIBED" : "❌
↳UNSUBSCRIBED") << std::endl;
std::cout << "  Camera Info:                "
    << (subscriptions_.at("head_rgbd_camera_info") ? "✓ SUBSCRIBED" : "❌
↳UNSUBSCRIBED") << std::endl;

std::cout << "\nBINOCULAR CAMERA SUBSCRIPTIONS:" << std::endl;
std::cout << "  Binocular Image:            "
    << (subscriptions_.at("binocular_image") ? "✓ SUBSCRIBED" : "❌
↳UNSUBSCRIBED") << std::endl;
std::cout << std::string(80, '=') << "\n"
    << std::endl;
}
```

(continues on next page)

(continued from previous page)

```
// Getters for sensor states
bool IsSensorOpen(const std::string& sensor_name) const {
    auto it = sensors_state_.find(sensor_name);
    return it != sensors_state_.end() && it->second;
}

private:
    sensor::SensorController& sensor_controller_;
    std::map<std::string, bool> sensors_state_;
    std::map<std::string, bool> subscriptions_;
};

void PrintMenu() {
    std::cout << "\n"
                << std::string(80, '=') << std::endl;
    std::cout << "MAGICBOT Z1 SENSOR CONTROL MENU" << std::endl;
    std::cout << std::string(80, '=') << std::endl;
    std::cout << "Sensor Open/Close:" << std::endl;
    std::cout << "  1 - Open LiDAR                      2 - Close LiDAR" << std::endl;
    std::cout << "  3 - Open Head RGBD Camera                4 - Close Head RGBD Camera" <<
    ↪std::endl;
    std::cout << "  5 - Open Binocular Camera                6 - Close Binocular Camera" <<
    ↪std::endl;
    std::cout << "\nLiDAR Subscriptions:" << std::endl;
    std::cout << "  i - Toggle LiDAR IMU                      p - Toggle LiDAR Point Cloud" <<
    ↪std::endl;
    std::cout << "\nHead RGBD Camera Subscriptions:" << std::endl;
    std::cout << "  c - Toggle Head Color Image                d - Toggle Head Depth Image" <<
    ↪std::endl;
    std::cout << "  C - Toggle Head Camera Info" << std::endl;
    std::cout << "\nBinocular Camera Subscriptions:" << std::endl;
    std::cout << "  b - Toggle Binocular Image" << std::endl;
    std::cout << "\nCommands:" << std::endl;
    std::cout << "  s - Show Status                          q - Quit                          ? - Help" <
    ↪std::endl;
    std::cout << std::string(80, '=') << std::endl;
}

int getch() {
    struct termios oldt, newt;
```

(continues on next page)

(continued from previous page)

```

    int ch;
    tcgetattr(STDIN_FILENO, &oldt);
    newt = oldt;
    newt.c_lflag &= ~(ICANON | ECHO);
    tcsetattr(STDIN_FILENO, TCSANOW, &newt);
    ch = getchar();
    tcsetattr(STDIN_FILENO, TCSANOW, &oldt);
    return ch;
}

int main() {
    // Bind SIGINT (Ctrl+C)
    signal(SIGINT, signalHandler);

    std::cout << "\n"
                << std::string(80, '=') << std::endl;
    std::cout << "MagicBot Z1 SDK Sensor Interactive Example" << std::endl;
    std::cout << "SDK Version: " << SDK_VERSION_STRING << std::endl;
    std::cout << std::string(80, '=') << "\n"
                << std::endl;

    std::string local_ip = "192.168.54.111";

    // Initialize robot SDK
    if (!robot.Initialize(local_ip)) {
        std::cerr << "[ERROR] Failed to initialize robot SDK" << std::endl;
        robot.Shutdown();
        return -1;
    }
    std::cout << "[INFO] ✓ Robot SDK initialized successfully" << std::endl;

    // Connect to robot
    auto status = robot.Connect();
    if (status.code != ErrorCode::OK) {
        std::cerr << "[ERROR] Failed to connect to robot, code: " << status.code
                    << ", message: " << status.message << std::endl;
        robot.Shutdown();
        return -1;
    }
    std::cout << "[INFO] ✓ Successfully connected to robot" << std::endl;

```

(continues on next page)

(continued from previous page)

```
// Get sensor controller
auto& sensor_controller = robot.GetSensorController();

// Initialize sensor controller
if (!sensor_controller.Initialize()) {
    std::cerr << "[ERROR] Failed to initialize sensor controller" << std::endl;
    robot.Disconnect();
    robot.Shutdown();
    return -1;
}
std::cout << "[INFO] ✓ Sensor controller initialized successfully\n"
          << std::endl;

// Create sensor manager
SensorManager sensor_manager(sensor_controller);

PrintMenu();

// Main loop
std::cout << "\nPress any key to continue..." << std::endl;

while (running) {
    int ch = getch();

    if (ch == 27 || ch == 'q' || ch == 'Q') { // ESC or 'q'
        std::cout << "\n[INFO] Quit key pressed, exiting program..." << std::endl;
        break;
    }

    // Sensor open/close control
    switch (ch) {
        case '1':
            sensor_manager.OpenLidar();
            break;
        case '2':
            sensor_manager.CloseLidar();
            break;
        case '3':
            sensor_manager.OpenHeadRgbCamera();
    }
}
```

(continues on next page)

(continued from previous page)

```

        break;
    case '4':
        sensor_manager.CloseHeadRgbCamera();
        break;
    case '5':
        sensor_manager.OpenBinocularCamera();
        break;
    case '6':
        sensor_manager.CloseBinocularCamera();
        break;

    // LiDAR subscriptions
    case 'i':
    case 'I':
        sensor_manager.ToggleLidarImuSubscription();
        break;
    case 'p':
    case 'P':
        sensor_manager.ToggleLidarPointCloudSubscription();
        break;

    // Head RGBD subscriptions
    case 'c':
        sensor_manager.ToggleHeadRgbColorImageSubscription();
        break;
    case 'd':
        sensor_manager.ToggleHeadRgbDepthImageSubscription();
        break;
    case 'C':
        sensor_manager.ToggleHeadRgbCameraInfoSubscription();
        break;

    // Binocular camera subscriptions
    case 'b':
        sensor_manager.ToggleBinocularImageSubscription();
        break;

    // Commands
    case 's':
    case 'S':

```

(continues on next page)



(continued from previous page)

```

        sensor_manager.ShowStatus();
        break;
    case '?':
        PrintMenu();
        break;

    default:
        // Ignore unknown keys
        break;
}
}

// Cleanup: close all sensors
std::cout << "\n"
            << std::string(80, '=') << std::endl;
std::cout << "Cleaning up resources..." << std::endl;
std::cout << std::string(80, '=') << std::endl;

if (sensor_manager.IsSensorOpen("lidar")) {
    sensor_manager.CloseLidar();
}
if (sensor_manager.IsSensorOpen("head_rgb_camera")) {
    sensor_manager.CloseHeadRgbCamera();
}
if (sensor_manager.IsSensorOpen("binocular_camera")) {
    sensor_manager.CloseBinocularCamera();
}

// Allow time for cleanup
usleep(500000); // 0.5 seconds

sensor_controller.Shutdown();
std::cout << "[INFO] ✓ Sensor controller shutdown" << std::endl;

status = robot.Disconnect();
if (status.code == ErrorCode::OK) {
    std::cout << "[INFO] ✓ Robot disconnected" << std::endl;
}

robot.Shutdown();

```

(continues on next page)

(continued from previous page)

```
std::cout << "[INFO] ✓ Robot shutdown" << std::endl;

std::cout << std::string(80, '=') << std::endl;
std::cout << "Cleanup complete" << std::endl;
std::cout << std::string(80, '=') << "\n"
        << std::endl;

return 0;
}
```

## 23.2 Python

Example file: sensor\_example.py

```
#!/usr/bin/env python3
# -*- coding: utf-8 -*-

import sys
import time
import signal
import logging
from typing import Optional

import magicbot_z1_python as magicbot

# Configure logging format and level
logging.basicConfig(
    level=logging.INFO,
    format="%(asctime)s [%(levelname)s] %(message)s",
    datefmt="%Y-%m-%d %H:%M:%S",
    force=True,
)

# Global variables
robot: Optional[magicbot.MagicRobot] = None
running = True

# Counters for data reception
lidar_imu_counter = 0
lidar_pointcloud_counter = 0
```

(continues on next page)

(continued from previous page)

```

head_rgbd_color_counter = 0
head_rgbd_depth_counter = 0
head_rgbd_camera_info_counter = 0
binocular_image_counter = 0
binocular_camera_info_counter = 0

def signal_handler(signum, frame):
    """Signal handler function for graceful exit"""
    global running, robot
    logging.info("Received interrupt signal (%s), exiting...", signum)
    running = False
    if robot:
        robot.disconnect()
        logging.info("Robot disconnected")
        robot.shutdown()
        logging.info("Robot shutdown")
    exit(-1)

class SensorManager:
    """Manages sensor subscriptions for MagicBot Z1"""

    def __init__(self, sensor_controller):
        self.sensor_controller = sensor_controller
        self.sensors_state = {
            "lidar": False,
            "head_rgbd_camera": False,
            "binocular_camera": False,
        }
        self.subscriptions = {
            # LiDAR subscriptions
            "lidar_imu": False,
            "lidar_point_cloud": False,
            # Head RGBD subscriptions
            "head_rgbd_color_image": False,
            "head_rgbd_depth_image": False,
            "head_rgbd_camera_info": False,
            # Binocular camera subscriptions
            "binocular_image": False,

```

(continues on next page)

(continued from previous page)

```

        "binocular_camera_info": False,
    }

# === LiDAR Control ===
def open_lidar(self) -> bool:
    """Open LiDAR"""
    if self.sensors_state["lidar"]:
        logging.warning("LiDAR already opened")
        return True

    status = self.sensor_controller.open_lidar()
    if status.code != magicbot.ErrorCode.OK:
        logging.error("Failed to open LiDAR: %s", status.message)
        return False

    self.sensors_state["lidar"] = True
    logging.info("✓ LiDAR opened successfully")
    return True

def close_lidar(self) -> bool:
    """Close LiDAR"""
    if not self.sensors_state["lidar"]:
        logging.warning("LiDAR already closed")
        return True

    status = self.sensor_controller.close_lidar()
    if status.code != magicbot.ErrorCode.OK:
        logging.error("Failed to close LiDAR: %s", status.message)
        return False

    self.sensors_state["lidar"] = False
    logging.info("✓ LiDAR closed")
    return True

# === Head RGBD Camera Control ===
def open_head_rgbd_camera(self) -> bool:
    """Open head RGBD camera"""
    if self.sensors_state["head_rgbd_camera"]:
        logging.warning("Head RGBD camera already opened")
        return True

```

(continues on next page)

(continued from previous page)

```

status = self.sensor_controller.open_head_rgbd_camera()
if status.code != magicbot.ErrorCode.OK:
    logging.error("Failed to open head RGBD camera: %s", status.message)
    return False

self.sensors_state["head_rgbd_camera"] = True
logging.info("✓ Head RGBD camera opened")
return True

def close_head_rgbd_camera(self) -> bool:
    """Close head RGBD camera"""
    if not self.sensors_state["head_rgbd_camera"]:
        logging.warning("Head RGBD camera already closed")
        return True

    status = self.sensor_controller.close_head_rgbd_camera()
    if status.code != magicbot.ErrorCode.OK:
        logging.error("Failed to close head RGBD camera: %s", status.message)
        return False

    self.sensors_state["head_rgbd_camera"] = False
    logging.info("✓ Head RGBD camera closed")
    return True

# === Binocular Camera Control ===
def open_binocular_camera(self) -> bool:
    """Open binocular camera"""
    if self.sensors_state["binocular_camera"]:
        logging.warning("Binocular camera already opened")
        return True

    status = self.sensor_controller.open_binocular_camera()
    if status.code != magicbot.ErrorCode.OK:
        logging.error("Failed to open binocular camera: %s", status.message)
        return False

    self.sensors_state["binocular_camera"] = True
    logging.info("✓ Binocular camera opened")
    return True

```

(continues on next page)

(continued from previous page)

```
def close_binocular_camera(self) -> bool:
    """Close binocular camera"""
    if not self.sensors_state["binocular_camera"]:
        logging.warning("Binocular camera already closed")
        return True

    status = self.sensor_controller.close_binocular_camera()
    if status.code != magicbot.ErrorCode.OK:
        logging.error("Failed to close binocular camera: %s", status.message)
        return False

    self.sensors_state["binocular_camera"] = False
    logging.info("✓ Binocular camera closed")
    return True

# === LiDAR Subscribe Methods ===
def toggle_lidar_imu_subscription(self):
    """Toggle LiDAR IMU subscription"""
    if self.subscriptions["lidar_imu"]:
        self.sensor_controller.unsubscribe_lidar_imu()
        self.subscriptions["lidar_imu"] = False
        logging.info("☐ LiDAR IMU unsubscribed")
    else:

        def lidar_imu_callback(imu):
            global lidar_imu_counter
            lidar_imu_counter += 1
            if lidar_imu_counter % 100 == 0:
                logging.info("===== LiDAR IMU Data =====")
                logging.info("Counter: %d", lidar_imu_counter)
                logging.info("Timestamp: %d", imu.timestamp)
                logging.info(
                    "Orientation (w,x,y,z): [%.4f, %.4f, %.4f, %.4f]",
                    imu.orientation[0],
                    imu.orientation[1],
                    imu.orientation[2],
                    imu.orientation[3],
                )
                logging.info(
```

(continues on next page)

(continued from previous page)

```

        "Angular velocity (x,y,z): [%.4f, %.4f, %.4f]",
        imu.angular_velocity[0],
        imu.angular_velocity[1],
        imu.angular_velocity[2],
    )
    logging.info(
        "Linear acceleration (x,y,z): [%.4f, %.4f, %.4f]",
        imu.linear_acceleration[0],
        imu.linear_acceleration[1],
        imu.linear_acceleration[2],
    )
    logging.info("Temperature: %.2f", imu.temperature)
    logging.info("=" * 40)

    self.sensor_controller.subscribe_lidar_imu(lidar_imu_callback)
    self.subscriptions["lidar_imu"] = True
    logging.info("✓ LiDAR IMU subscribed")

def toggle_lidar_point_cloud_subscription(self):
    """Toggle LiDAR point cloud subscription"""
    if self.subscriptions["lidar_point_cloud"]:
        self.sensor_controller.unsubscribe_lidar_point_cloud()
        self.subscriptions["lidar_point_cloud"] = False
        logging.info("☐ LiDAR point cloud unsubscribed")
    else:

def lidar_pointcloud_callback(pointcloud):
    global lidar_pointcloud_counter
    lidar_pointcloud_counter += 1
    if lidar_pointcloud_counter % 10 == 0:
        logging.info("===== LiDAR Point Cloud =====")
        logging.info("Counter: %d", lidar_pointcloud_counter)
        logging.info("Data size: %d bytes", len(pointcloud.data))
        logging.info("Width: %d", pointcloud.width)
        logging.info("Height: %d", pointcloud.height)
        logging.info("Is dense: %s", pointcloud.is_dense)
        logging.info("Point step: %d", pointcloud.point_step)
        logging.info("Row step: %d", pointcloud.row_step)
        logging.info("Number of fields: %d", len(pointcloud.fields))
        if pointcloud.fields:

```

(continues on next page)

(continued from previous page)

```

        logging.info("First field name: %s", pointcloud.fields[0].
↪name)

        logging.info("=" * 40)

        self.sensor_controller.subscribe_lidar_point_cloud(
            lidar_pointcloud_callback
        )
        self.subscriptions["lidar_point_cloud"] = True
        logging.info("✓ LiDAR point cloud subscribed")

# === Head RGBD Subscribe Methods ===
def toggle_head_rgbd_color_image_subscription(self):
    """Toggle head RGBD color image subscription"""
    if self.subscriptions["head_rgbd_color_image"]:
        self.sensor_controller.unsubscribe_head_rgbd_color_image()
        self.subscriptions["head_rgbd_color_image"] = False
        logging.info("☒ Head RGBD color image unsubscribed")
    else:

        def head_rgbd_color_image_callback(img):
            global head_rgbd_color_counter
            head_rgbd_color_counter += 1
            if head_rgbd_color_counter % 15 == 0:
                logging.info("===== Head RGBD Color Image =====")
                logging.info("Counter: %d", head_rgbd_color_counter)
                logging.info("Size: %d bytes", len(img.data))
                logging.info("Resolution: %dx%d", img.width, img.height)
                logging.info("Encoding: %s", img.encoding)
                logging.info("=" * 40)

        self.sensor_controller.subscribe_head_rgbd_color_image(
            head_rgbd_color_image_callback
        )
        self.subscriptions["head_rgbd_color_image"] = True
        logging.info("✓ Head RGBD color image subscribed")

def toggle_head_rgbd_depth_image_subscription(self):
    """Toggle head RGBD depth image subscription"""
    if self.subscriptions["head_rgbd_depth_image"]:
        self.sensor_controller.unsubscribe_head_rgbd_depth_image()

```

(continues on next page)



(continued from previous page)

```

        self.subscriptions["head_rgbd_depth_image"] = False
        logging.info("❌ Head RGBD depth image unsubscribed")
    else:

        def head_rgbd_depth_image_callback(img):
            global head_rgbd_depth_counter
            head_rgbd_depth_counter += 1
            if head_rgbd_depth_counter % 15 == 0:
                logging.info("===== Head RGBD Depth Image =====")
                logging.info("Counter: %d", head_rgbd_depth_counter)
                logging.info("Size: %d bytes", len(img.data))
                logging.info("Resolution: %dx%d", img.width, img.height)
                logging.info("Encoding: %s", img.encoding)
                logging.info("=" * 40)

        self.sensor_controller.subscribe_head_rgbd_depth_image(
            head_rgbd_depth_image_callback
        )
        self.subscriptions["head_rgbd_depth_image"] = True
        logging.info("✅ Head RGBD depth image subscribed")

    def toggle_head_rgbd_camera_info_subscription(self):
        """Toggle head RGBD camera info subscription"""
        if self.subscriptions["head_rgbd_camera_info"]:
            self.sensor_controller.unsubscribe_head_rgbd_camera_info()
            self.subscriptions["head_rgbd_camera_info"] = False
            logging.info("❌ Head RGBD camera info unsubscribed")
        else:

            def head_rgbd_camera_info_callback(info):
                global head_rgbd_camera_info_counter
                head_rgbd_camera_info_counter += 1
                logging.info("===== Head RGBD Camera Info =====")
                logging.info("Counter: %d", head_rgbd_camera_info_counter)
                logging.info("Resolution: %dx%d", info.width, info.height)
                logging.info("Distortion model: %s", info.distortion_model)
                logging.info("=" * 40)

            self.sensor_controller.subscribe_head_rgbd_camera_info(
                head_rgbd_camera_info_callback
            )
            self.subscriptions["head_rgbd_camera_info"] = True
            logging.info("✅ Head RGBD camera info subscribed")

```

(continues on next page)

(continued from previous page)

```

    )

    self.subscriptions["head_rgbd_camera_info"] = True
    logging.info("✓ Head RGBD camera info subscribed")

# === Binocular Camera Subscribe Methods ===
def toggle_binocular_image_subscription(self):
    """Toggle binocular camera image subscription"""
    if self.subscriptions["binocular_image"]:
        self.sensor_controller.unsubscribe_binocular_image()
        self.subscriptions["binocular_image"] = False
        logging.info("✗ Binocular image unsubscribed")
    else:

        def binocular_image_callback(frame):
            global binocular_image_counter
            binocular_image_counter += 1
            if binocular_image_counter % 15 == 0:
                logging.info("===== Binocular Camera Image =====")
                logging.info("Counter: %d", binocular_image_counter)
                logging.info("Timestamp: %d", frame.header.stamp)
                logging.info("Frame ID: %s", frame.header.frame_id)
                logging.info("Format: %s", frame.format)
                logging.info(
                    "Data size: %d bytes (left+right concatenated)",
                    len(frame.data),
                )
                logging.info("=" * 40)

            self.sensor_controller.subscribe_binocular_image(binocular_image_callback)
            self.subscriptions["binocular_image"] = True
            logging.info("✓ Binocular image subscribed")

def toggle_binocular_camera_info_subscription(self):
    """Toggle binocular camera info subscription"""
    if self.subscriptions["binocular_camera_info"]:
        self.sensor_controller.unsubscribe_binocular_camera_info()
        self.subscriptions["binocular_camera_info"] = False
        logging.info("✗ Binocular camera info unsubscribed")
    else:

```

(continues on next page)

(continued from previous page)

```
def binocular_camera_info_callback(info):
    global binocular_camera_info_counter
    binocular_camera_info_counter += 1
    logging.info("==== Binocular Camera Info =====")
    logging.info("Counter: %d", binocular_camera_info_counter)
    logging.info("Resolution: %dx%d", info.width, info.height)
    logging.info("Distortion model: %s", info.distortion_model)
    logging.info("=" * 40)

    self.sensor_controller.subscribe_binocular_camera_info(
        binocular_camera_info_callback
    )
    self.subscriptions["binocular_camera_info"] = True
    logging.info("✓ Binocular camera info subscribed")

def show_status(self):
    """Display current sensor status"""
    logging.info("\n" + "=" * 80)
    logging.info("MAGICBOT Z1 SENSOR STATUS")
    logging.info("=" * 80)
    logging.info(
        "LiDAR: %s",
        "OPEN" if self.sensors_state["lidar"] else "CLOSED",
    )
    logging.info(
        "Head RGBD Camera: %s",
        "OPEN" if self.sensors_state["head_rgbd_camera"] else "CLOSED",
    )
    logging.info(
        "Binocular Camera: %s",
        "OPEN" if self.sensors_state["binocular_camera"] else "CLOSED",
    )
    logging.info("\nLIDAR SUBSCRIPTIONS:")
    logging.info(
        "  LiDAR IMU: %s",
        "✓ SUBSCRIBED" if self.subscriptions["lidar_imu"] else "✗ UNSUBSCRIBED",
    )
    logging.info(
        "  LiDAR Point Cloud: %s",
        (
```

(continues on next page)

(continued from previous page)

```

        "✓ SUBSCRIBED"
        if self.subscriptions["lidar_point_cloud"]
        else "✗ UNSUBSCRIBED"
    ),
)
logging.info("\nHEAD RGBD SUBSCRIPTIONS:")
logging.info(
    "  Color Image:           %s",
    (
        "✓ SUBSCRIBED"
        if self.subscriptions["head_rgbd_color_image"]
        else "✗ UNSUBSCRIBED"
    ),
)
logging.info(
    "  Depth Image:          %s",
    (
        "✓ SUBSCRIBED"
        if self.subscriptions["head_rgbd_depth_image"]
        else "✗ UNSUBSCRIBED"
    ),
)
logging.info(
    "  Camera Info:          %s",
    (
        "✓ SUBSCRIBED"
        if self.subscriptions["head_rgbd_camera_info"]
        else "✗ UNSUBSCRIBED"
    ),
)
logging.info("\nBINOCULAR CAMERA SUBSCRIPTIONS:")
logging.info(
    "  Binocular Image:       %s",
    (
        "✓ SUBSCRIBED"
        if self.subscriptions["binocular_image"]
        else "✗ UNSUBSCRIBED"
    ),
)
logging.info(

```

(continues on next page)

(continued from previous page)

```

        " Camera Info:                                %s",
        (
            "✓ SUBSCRIBED"
            if self.subscriptions["binocular_camera_info"]
            else "✗ UNSUBSCRIBED"
        ),
    )
    logging.info("=" * 80 + "\n")

def print_menu():
    """Print interactive menu"""
    logging.info("\n" + "=" * 80)
    logging.info("MAGICBOT Z1 SENSOR CONTROL MENU")
    logging.info("=" * 80)
    logging.info("Sensor Open/Close:")
    logging.info("  1 - Open LiDAR                                2 - Close LiDAR")
    logging.info("  3 - Open Head RGBD Camera                        4 - Close Head RGBD Camera")
    logging.info("  5 - Open Binocular Camera                        6 - Close Binocular Camera")
    logging.info("\nLiDAR Subscriptions:")
    logging.info("  i - Toggle LiDAR IMU                                p - Toggle LiDAR Point Cloud")
    logging.info("\nHead RGBD Camera Subscriptions:")
    logging.info("  c - Toggle Head Color Image                        d - Toggle Head Depth Image")
    logging.info("  C - Toggle Head Camera Info")
    logging.info("\nBinocular Camera Subscriptions:")
    logging.info(
        "  b - Toggle Binocular Image                        B - Toggle Binocular Camera Info"
    )
    logging.info("\nCommands:")
    logging.info(
        "  s - Show Status                                ESC - Quit                                ? - Help"
    )
    logging.info("=" * 80)

def main():
    """Main function"""
    global robot, running

    # Bind signal handler

```

(continues on next page)

(continued from previous page)

```

signal.signal(signal.SIGINT, signal_handler)

logging.info("\n" + "=" * 80)
logging.info("MagicBot Z1 SDK Sensor Interactive Example")
logging.info("Robot Model: %s", magicbot.get_robot_model())

# Create robot instance
robot = magicbot.MagicRobot()
logging.info("SDK Version: %s", robot.get_sdk_version())
logging.info("=" * 80 + "\n")

try:
    # Configure local IP address for direct network connection and initialize SDK
    local_ip = "192.168.54.111"
    if not robot.initialize(local_ip):
        logging.error("Failed to initialize robot SDK")
        robot.shutdown()
        return -1

    logging.info("✓ Robot SDK initialized successfully")

    # Connect to robot
    status = robot.connect()
    if status.code != magicbot.ErrorCode.OK:
        logging.error(
            "Failed to connect to robot, code: %s, message: %s",
            status.code,
            status.message,
        )
        robot.shutdown()
        return -1

    logging.info("✓ Successfully connected to robot")

    # Get sensor controller
    sensor_controller = robot.get_sensor_controller()

    # Initialize sensor controller
    if not sensor_controller.initialize():
        logging.error("Failed to initialize sensor controller")

```

(continues on next page)

(continued from previous page)

```

robot.disconnect()
robot.shutdown()
return -1

logging.info("✓ Sensor controller initialized successfully\n")

sensor_manager = SensorManager(sensor_controller)

print_menu()

while running:
    try:
        choice = input("\nEnter your choice: ").strip()

        if choice == "\x1b" or choice.lower() == "esc": # ESC key
            logging.info("ESC key pressed, exiting program...")
            break

        # Sensor open/close control
        if choice == "1":
            sensor_manager.open_lidar()
        elif choice == "2":
            sensor_manager.close_lidar()
        elif choice == "3":
            sensor_manager.open_head_rgbd_camera()
        elif choice == "4":
            sensor_manager.close_head_rgbd_camera()
        elif choice == "5":
            sensor_manager.open_binocular_camera()
        elif choice == "6":
            sensor_manager.close_binocular_camera()

        # LiDAR subscriptions
        elif choice == "i":
            sensor_manager.toggle_lidar_imu_subscription()
        elif choice == "p":
            sensor_manager.toggle_lidar_point_cloud_subscription()

        # Head RGBD subscriptions
        elif choice == "c":

```

(continues on next page)

(continued from previous page)

```

        sensor_manager.toggle_head_rgbd_color_image_subscription()
    elif choice == "d":
        sensor_manager.toggle_head_rgbd_depth_image_subscription()
    elif choice == "C":
        sensor_manager.toggle_head_rgbd_camera_info_subscription()

    # Binocular camera subscriptions
    elif choice == "b":
        sensor_manager.toggle_binocular_image_subscription()
    elif choice == "B":
        sensor_manager.toggle_binocular_camera_info_subscription()
    # Commands
    elif choice.lower() == "s":
        sensor_manager.show_status()
    elif choice == "?" or choice.lower() == "help":
        print_menu()
    elif choice == "":
        continue
    else:
        logging.warning("Invalid choice: '%s'. Press '?' for help.",
↪choice)

except KeyboardInterrupt:
    logging.info("\nReceived keyboard interrupt, shutting down...")
    break
except EOFError:
    logging.info("\nReceived EOF, shutting down...")
    break
except Exception as e:
    logging.error("Error occurred while processing input: %s", e)

except Exception as e:
    logging.error("Exception occurred during program execution: %s", e)
    import traceback

    traceback.print_exc()
    return -1

finally:
    # Cleanup: close all sensors

```

(continues on next page)



(continued from previous page)

```

logging.info("\n" + "=" * 80)
logging.info("Cleaning up resources...")
logging.info("=" * 80)

try:
    # Close all sensors
    if sensor_manager.sensors_state["lidar"]:
        sensor_manager.close_lidar()
    if sensor_manager.sensors_state["head_rgbd_camera"]:
        sensor_manager.close_head_rgbd_camera()
    if sensor_manager.sensors_state["binocular_camera"]:
        sensor_manager.close_binocular_camera()

    # Allow time for cleanup
    time.sleep(0.5)

    sensor_controller.shutdown()
    logging.info("✓ Sensor controller shutdown")

    robot.disconnect()
    logging.info("✓ Robot disconnected")

    robot.shutdown()
    logging.info("✓ Robot shutdown")

    logging.info("=" * 80)
    logging.info("Cleanup complete")
    logging.info("=" * 80 + "\n")

except Exception as e:
    logging.error("Exception occurred while cleaning up resources: %s", e)

return 0

if __name__ == "__main__":
    sys.exit(main())
    
```

## 23.3 Running Instructions

### 23.3.1 Environment Setup

```
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH
```

### 23.3.2 Run Example

```
# C++
./sensor_example
# Python
python3 sensor_example.py
```

### 23.3.3 Control Instructions

- Sensor On/Off Control:
  - 1 - Open LiDAR
  - 2 - Close LiDAR
  - 3 - Open head RGBD camera
  - 4 - Close head RGBD camera
  - 5 - Open binocular camera
  - 6 - Close binocular camera
- LiDAR Data Subscription:
  - i - Toggle IMU data subscription
  - p - Toggle point cloud data subscription
- Head RGBD Camera Data Subscription:
  - c - Toggle color image subscription
  - C - Toggle color camera parameters subscription
  - d - Toggle depth image subscription
  - D - Toggle depth camera parameters subscription
- Binocular Camera Data Subscription:
  - b - Toggle image subscription
- Other Commands:

- s - Show current status
- ? - Show help menu

### 23.3.4 Stop Program

- Press `ESC` to safely stop the program
- The program will automatically clean up all resources



---

## Audio Control Example

---

This example demonstrates how to use the Magicbot-Z1 SDK for initialization, robot connection, audio control (get volume, set volume, TTS playback, audio stream subscription), and other basic operations.

### 24.1 C++

Example file: `audio_example.cpp`

```
#include "magic_robot.h"
#include "magic_sdk_version.h"

#include <termios.h>
#include <unistd.h>
#include <csignal>

#include <iostream>

using namespace magic::z1;

magic::z1::MagicRobot robot;

void signalHandler(int signum) {
    std::cout << "Interrupt signal (" << signum << ") received.\n";
```

(continues on next page)

(continued from previous page)

```

robot.Shutdown();
// Exit process
exit(signum);
}

void print_help() {
    std::cout << "Key Function Description:\n";
    std::cout << "  Audio Functions:\n";
    std::cout << "  1      Function 1: Get volume\n";
    std::cout << "  2      Function 2: Set volume\n";
    std::cout << "  3      Function 3: Play TTS\n";
    std::cout << "  4      Function 4: Stop playback\n";
    std::cout << "  Audio stream Functions:\n";
    std::cout << "  5      Function 5: Open audio stream\n";
    std::cout << "  6      Function 6: Close audio stream\n";
    std::cout << "  7      Function 7: Subscribe to audio stream\n";
    std::cout << "  8      Function 8: Unsubscribe to audio stream\n";
    std::cout << "  Wakeup Status Functions:\n";
    std::cout << "  q      Function q: Open wakeup status stream\n";
    std::cout << "  w      Function w: Close wakeup status stream\n";
    std::cout << "  e      Function e: Subscribe to wakeup status\n";
    std::cout << "  r      Function r: Unsubscribe to wakeup status\n";
    std::cout << "\n";
    std::cout << "  ?      Function ?: Print help\n";
    std::cout << "  ESC    Exit program\n";
}

int getch() {
    struct termios oldt, newt;
    int ch;
    tcgetattr(STDIN_FILENO, &oldt); // Get current terminal settings
    newt = oldt;
    newt.c_lflag &= ~(ICANON | ECHO); // Disable buffering and echo
    tcsetattr(STDIN_FILENO, TCSANOW, &newt);
    ch = getchar(); // Read key press
    tcsetattr(STDIN_FILENO, TCSANOW, &oldt); // Restore settings
    return ch;
}

```

(continues on next page)

(continued from previous page)

```

void GetVolume() {
    // Get audio controller
    auto& controller = robot.GetAudioController();

    // Get volume
    int get_volume = 0;
    auto status = controller.GetVolume(get_volume);
    if (status.code != ErrorCode::OK) {
        std::cerr << "get volume failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }
    std::cout << "get volume success, volume: " << std::to_string(get_volume) << "\n";
    std::endl;
}

void SetVolume() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Set volume
    auto status = controller.SetVolume(50);
    if (status.code != ErrorCode::OK) {
        std::cerr << "set volume failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }
    std::cout << "set volume success" << std::endl;
}

void PlayTts() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Play speech
    TtsCommand tts;
    tts.id = "100000000001";
    tts.content = "How's the weather today!";
    tts.priority = TtsPriority::HIGH;
    tts.mode = TtsMode::CLEARTOP;
}

```

(continues on next page)

(continued from previous page)

```
    auto status = controller.Play(tts);
    if (status.code != ErrorCode::OK) {
        std::cerr << "play tts failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }
    std::cout << "play tts success" << std::endl;
}

void StopTts() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Stop speech playback
    auto status = controller.Stop();
    if (status.code != ErrorCode::OK) {
        std::cerr << "stop tts failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }
    std::cout << "stop tts success" << std::endl;
}

void OpenAudioStream() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Open audio stream
    auto status = controller.OpenAudioStream();
    if (status.code != ErrorCode::OK) {
        std::cerr << "open audio stream failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }
    std::cout << "open audio stream success" << std::endl;
}

void CloseAudioStream() {
    // Get audio controller
```

(continues on next page)



(continued from previous page)

```

    auto& controller = robot.GetAudioController();
    // Close audio stream
    auto status = controller.CloseAudioStream();
    if (status.code != ErrorCode::OK) {
        std::cerr << "close audio stream failed"
                    << ", code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }
    std::cout << "close audio stream success" << std::endl;
}

void SubscribeAudioStream() {
    // Get audio controller
    auto& controller = robot.GetAudioController();

    // Subscribe to audio streams
    controller.SubscribeOriginAudioStream([] (const std::shared_ptr<AudioStream> data) {
        static int32_t counter = 0;
        if (counter++ % 30 == 0) {
            std::cout << "Received origin audio stream data, size: " << data->data_length <
↳< std::endl;
        }
    });

    controller.SubscribeBfAudioStream([] (const std::shared_ptr<AudioStream> data) {
        static int32_t counter = 0;
        if (counter++ % 30 == 0) {
            std::cout << "Received bf audio stream data, size: " << data->data_length <<↳
↳std::endl;
        }
    });
    std::cout << "Subscribed to audio streams" << std::endl;
}

void UnsubscribeAudioStream() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Unsubscribe from audio streams
    controller.UnsubscribeOriginAudioStream();
}

```

(continues on next page)

(continued from previous page)

```

    controller.UnsubscribeBfAudioStream();
    std::cout << "Unsubscribed from audio streams" << std::endl;
}

void OpenWakeupStatusStream() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Open wakeup status stream
    auto status = controller.OpenWakeupStatusStream();
}

void CloseWakeupStatusStream() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Close wakeup status stream
    auto status = controller.CloseWakeupStatusStream();
}

void SubscribeWakeupStatus() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Subscribe to wakeup status
    controller.SubscribeWakeupStatus([](const std::shared_ptr<WakeupStatus> data) {
        static int32_t counter = 0;
        if (data->is_wakeup) {
            if (data->enable_wakeup_orientation) {
                std::cout << "Received wakeup status data, is_wakeup: " << data->is_wakeup <<
↳", enable_wakeup_orientation: " << data->enable_wakeup_orientation << ", wakeup_
↳orientation: " << data->wakeup_orientation << std::endl;
            } else {
                std::cout << "Received wakeup status data, is_wakeup: " << data->is_wakeup <<
↳std::endl;
            }
        } else {
            std::cout << "Received wakeup status data, is_wakeup: " << data->is_wakeup <<
↳std::endl;
        }
    });
}

```

(continues on next page)

(continued from previous page)

```
void UnsubscribeWakeupStatus() {
    // Get audio controller
    auto& controller = robot.GetAudioController();
    // Unsubscribe from wakeup status
    controller.UnsubscribeWakeupStatus();
}

int main(int argc, char* argv[]) {
    // Bind SIGINT (Ctrl+C)
    signal(SIGINT, signalHandler);

    std::cout << "SDK Version: " << SDK_VERSION_STRING << std::endl;

    print_help();

    std::string local_ip = "192.168.54.111";
    // Configure local IP address for direct network connection and initialize SDK
    if (!robot.Initialize(local_ip)) {
        std::cerr << "robot sdk initialize failed." << std::endl;
        robot.Shutdown();
        return -1;
    }

    // Connect to robot
    auto status = robot.Connect();
    if (status.code != ErrorCode::OK) {
        std::cerr << "connect robot failed"
            << ", code: " << status.code
            << ", message: " << status.message << std::endl;
        robot.Shutdown();
        return -1;
    }

    std::cout << "Press any key to continue (ESC to exit)..."
        << std::endl;

    // Wait for user input
    while (1) {
        int key = getch();
        if (key == 27)
            break; // ESC key ASCII code is 27
    }
}
```

(continues on next page)

(continued from previous page)

```
std::cout << "Key ASCII: " << key << ", Character: " << static_cast<char>(key) << "\n";
std::endl;

switch (key) {
    // 1. Audio Functions
    case '1': {
        // Get volume
        GetVolume();
        break;
    }
    case '2': {
        // Set volume
        SetVolume();
        break;
    }
    case '3': {
        PlayTts();
        break;
    }
    case '4': {
        StopTts();
        break;
    }
    // 2. Audio stream Functions
    case '5': {
        OpenAudioStream();
        break;
    }
    case '6': {
        CloseAudioStream();
        break;
    }
    case '7': {
        SubscribeAudioStream();
        break;
    }
    case '8': {
        UnsubscribeAudioStream();
        break;
    }
}
```

(continues on next page)

(continued from previous page)

```
// 3. Wakeup Status Functions
case 'Q':
case 'q': {
    OpenWakeupStatusStream();
    break;
}
case 'W':
case 'w': {
    CloseWakeupStatusStream();
    break;
}
case 'E':
case 'e': {
    SubscribeWakeupStatus();
    break;
}
case 'R':
case 'r': {
    UnsubscribeWakeupStatus();
    break;
}
case '?': {
    print_help();
    break;
}
default:
    std::cout << "Unknown key: " << key << std::endl;
    break;
}
usleep(10000);
}

// Disconnect from robot
status = robot.Disconnect();
if (status.code != ErrorCode::OK) {
    std::cerr << "disconnect robot failed"
        << ", code: " << status.code
        << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}
```

(continues on next page)

(continued from previous page)

```
}

robot.Shutdown();

return 0;
}
```

## 24.2 Python

Example file: audio\_example.py

```
#!/usr/bin/env python3
# -*- coding: utf-8 -*-

import sys
import time
import signal
import threading
import logging
from typing import Optional

import magicbot_z1_python as magicbot

# Configure logging format and level
logging.basicConfig(
    level=logging.INFO, # Minimum log level
    format="%(asctime)s [%(levelname)s] %(message)s",
    datefmt="%Y-%m-%d %H:%M:%S",
)

# Global variables
robot: Optional[magicbot.MagicRobot] = None
running = True

def signal_handler(signum, frame):
    """Signal handler function for graceful exit"""
    global running, robot
    logging.info("Received interrupt signal (%s), exiting...", signum)
    running = False
```

(continues on next page)

(continued from previous page)

```

if robot:
    robot.shutdown()
    logging.info("Robot shutdown")
exit(-1)

def print_help():
    """Print help information"""
    logging.info("Key Function Demo Program")
    logging.info("")
    logging.info("Audio Functions:")
    logging.info(" 1      Function 1: Get volume")
    logging.info(" 2      Function 2: Set volume")
    logging.info(" 3      Function 3: Play TTS")
    logging.info(" 4      Function 4: Stop playback")
    logging.info("")
    logging.info("Audio stream Functions:")
    logging.info(" 5      Function 5: Open audio stream")
    logging.info(" 6      Function 6: Close audio stream")
    logging.info(" 7      Function 7: Subscribe to audio stream")
    logging.info(" 8      Function 8: Unsubscribe to audio stream")
    logging.info("")
    logging.info("Wakeup Status Functions:")
    logging.info(" Q      Function Q: Open wakeup status stream")
    logging.info(" W      Function W: Close wakeup status stream")
    logging.info(" E      Function E: Subscribe to wakeup status")
    logging.info(" R      Function R: Unsubscribe to wakeup status")
    logging.info("")
    logging.info(" ?      Function ?: Print help")
    logging.info(" ESC    Exit program")

def get_volume():
    """Get volume"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Get volume

```

(continues on next page)

(continued from previous page)

```
status, volume = controller.get_volume()
if status.code != magicbot.ErrorCode.OK:
    logging.error(
        "Failed to get volume, code: %s, message: %s",
        status.code,
        status.message,
    )
    return

logging.info("Successfully got volume, volume: %s", volume)
except Exception as e:
    logging.error("Exception occurred while getting volume: %s", e)

def set_volume(volume):
    """Set volume"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Set volume to 7
        status = controller.set_volume(volume)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to set volume, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        logging.info("Successfully set volume")
    except Exception as e:
        logging.error("Exception occurred while setting volume: %s", e)

def play_tts(content):
    """Play TTS speech"""
    global robot
    try:
```

(continues on next page)



(continued from previous page)

```

    # Get audio controller
    controller = robot.get_audio_controller()

    # Create TTS command
    tts = magicbot.TtsCommand()
    tts.id = "100000000001"
    tts.content = content
    tts.priority = magicbot.TtsPriority.HIGH
    tts.mode = magicbot.TtsMode.CLEARTOP

    # Play speech
    status = controller.play(tts)
    if status.code != magicbot.ErrorCode.OK:
        logging.error(
            "Failed to play TTS, code: %s, message: %s", status.code, status.
↪message
        )
        return

    logging.info("Successfully played TTS")
except Exception as e:
    logging.error("Exception occurred while playing TTS: %s", e)

def stop_tts():
    """Stop TTS playback"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Stop speech playback
        status = controller.stop()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to stop TTS, code: %s, message: %s", status.code, status.
↪message
            )
        return

```

(continues on next page)

(continued from previous page)

```
        logging.info("Successfully stopped TTS")
    except Exception as e:
        logging.error("Exception occurred while stopping TTS: %s", e)

def open_audio_stream():
    """Open audio stream"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Open audio stream
        status = controller.open_audio_stream()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to open audio stream, code: %s, message: %s",
                status.code,
                status.message,
            )
        return

        logging.info("Successfully opened audio stream")
    except Exception as e:
        logging.error("Exception occurred while opening audio stream: %s", e)

def close_audio_stream():
    """Close audio stream"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Close audio stream
        status = controller.close_audio_stream()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to close audio stream, code: %s, message: %s",
                status.code,
```

(continues on next page)

(continued from previous page)

```

        status.message,
    )
    return

    logging.info("Successfully closed audio stream")
except Exception as e:
    logging.error("Exception occurred while closing audio stream: %s", e)

def subscribe_audio_stream():
    """Subscribe to audio stream"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Audio stream counters
        origin_counter = 0
        bf_counter = 0

        def origin_audio_callback(audio_stream):
            """Original audio stream callback function"""
            nonlocal origin_counter
            if origin_counter % 30 == 0:
                logging.info(
                    "Received original audio stream data, size: %d",
                    audio_stream.data_length,
                )
                sys.stdout.write("\r")
                sys.stdout.flush()
                origin_counter += 1

        def bf_audio_callback(audio_stream):
            """BF audio stream callback function"""
            nonlocal bf_counter
            if bf_counter % 30 == 0:
                logging.info(
                    "Received BF audio stream data, size: %d", audio_stream.data_
↪length
                )
    
```

(continues on next page)

(continued from previous page)

```

        sys.stdout.write("\r")
        sys.stdout.flush()
        bf_counter += 1

    # Subscribe to audio streams
    controller.subscribe_origin_audio_stream(origin_audio_callback)
    controller.subscribe_bf_audio_stream(bf_audio_callback)

    logging.info("Subscribed to audio streams")
except Exception as e:
    logging.error("Exception occurred while subscribing to audio stream: %s", e)

def unsubscribe_audio_stream():
    """Unsubscribe to audio stream"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Unsubscribe to audio stream
        controller.unsubscribe_bf_audio_stream()
        controller.unsubscribe_origin_audio_stream()

        logging.info("Unsubscribed to audio stream")
    except Exception as e:
        logging.error("Exception occurred while unsubscribing to audio stream: %s", e)

def open_wakeup_status_stream():
    """Open wakeup status stream"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Open wakeup status stream
        status = controller.open_wakeup_status_stream()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(

```

(continues on next page)

(continued from previous page)

```

        "Failed to open wakeup status stream, code: %s, message: %s",
        status.code,
        status.message,
    )
    return

    logging.info("Successfully opened wakeup status stream")
except Exception as e:
    logging.error("Exception occurred while opening wakeup status stream: %s", e)

def close_wakeup_status_stream():
    """Close wakeup status stream"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Close wakeup status stream
        status = controller.close_wakeup_status_stream()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to close wakeup status stream, code: %s, message: %s",
                status.code,
                status.message,
            )
        return

        logging.info("Successfully closed wakeup status stream")
    except Exception as e:
        logging.error("Exception occurred while closing wakeup status stream: %s", e)

def unsubscribe_wakeup_status():
    """Unsubscribe to wakeup status"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

```

(continues on next page)

(continued from previous page)

```

    # Unsubscribe to wakeup status
    controller.unsubscribe_wakeup_status()

    logging.info("Unsubscribed to wakeup status")
    except Exception as e:
        logging.error("Exception occurred while unsubscribing to wakeup status: %s",
↳e)

def subscribe_wakeup_status():
    """Subscribe to wakeup status"""
    global robot
    try:
        # Get audio controller
        controller = robot.get_audio_controller()

        # Wakeup status counter
        wakeup_counter = 0

    def wakeup_status_callback(wakeup_status):
        """Wakeup status callback function"""
        nonlocal wakeup_counter
        if wakeup_status.is_wakeup:
            if wakeup_status.enable_wakeup_orientation:
                logging.info(
                    "Voice wakeup detected! Orientation: %.2f radians (%.1f
↳degrees)",
                    wakeup_status.wakeup_orientation,
                    wakeup_status.wakeup_orientation * 180.0 / 3.14159,
                )
            else:
                logging.info("Voice wakeup detected!")
                sys.stdout.write("\r")
                sys.stdout.flush()
        else:
            if wakeup_counter % 10 == 0: # Log every 50th non-wakeup status
                logging.info(
                    "Wakeup status: sleeping, enable_wakeup_orientation: %s,
↳orientation: %.2f radians",
                    wakeup_status.enable_wakeup_orientation,

```

(continues on next page)

(continued from previous page)

```

        wakeup_status.wakeup_orientation * 180.0 / 3.14159,
    )
    sys.stdout.write("\r")
    sys.stdout.flush()
    wakeup_counter += 1

    # Subscribe to wakeup status
    controller.subscribe_wakeup_status(wakeup_status_callback)

    logging.info("Subscribed to wakeup status stream")
except Exception as e:
    logging.error("Exception occurred while subscribing to wakeup status: %s", e)

def get_user_input():
    """Get user input - Read a single line of data"""
    try:
        # Method 1: Read a line using input() (recommended)
        return input("Enter command: ").strip()
    except (EOFError, KeyboardInterrupt):
        return ""

def main():
    """Main function"""
    global robot, running

    # Bind signal handler
    signal.signal(signal.SIGINT, signal_handler)

    logging.info("Robot model: %s", magicbot.get_robot_model())

    # Create robot instance
    robot = magicbot.MagicRobot()

    try:
        # Configure local IP address for direct network connection and initialize SDK
        local_ip = "192.168.54.111"
        if not robot.initialize(local_ip):
            logging.error("Failed to initialize robot SDK")

```

(continues on next page)

(continued from previous page)

```
robot.shutdown()
return -1

# Connect to robot
status = robot.connect()
if status.code != magicbot.ErrorCode.OK:
    logging.error(
        "Failed to connect to robot, code: %s, message: %s",
        status.code,
        status.message,
    )
    robot.shutdown()
    return -1

logging.info("Successfully connected to robot")

# Initialize audio controller
audio_controller = robot.get_audio_controller()
if not audio_controller.initialize():
    logging.error("Failed to initialize audio controller")
    robot.disconnect()
    robot.shutdown()
    return -1

logging.info("Successfully initialized audio controller")
print_help()
logging.info("Press any key to continue (ESC to exit)...")

# Main loop
while running:
    try:
        str_input = get_user_input()

        # Split input parameters by space
        parts = str_input.strip().split()

        if not parts:
            time.sleep(0.01) # Brief delay
            continue
```

(continues on next page)



(continued from previous page)

```
# Parse parameters
key = parts[0]
args = parts[1:] if len(parts) > 1 else []
if key == "\x1b": # ESC key
    break
# 1. Audio Functions
# 1.1 Get volume
if key == "1":
    get_volume()
# 1.2 Set volume
elif key == "2":
    volume = args[0] if args else 50
    set_volume(volume)
# 1.3 Play TTS
elif key == "3":
    content = args[0] if args else "How's the weather today!"
    play_tts(content)
# 1.4 Stop TTS
elif key == "4":
    stop_tts()
# 2. Audio Stream Functions
# 2.1 Open audio stream
elif key == "5":
    open_audio_stream()
# 2.2 Close audio stream
elif key == "6":
    close_audio_stream()
# 2.3 Subscribe to audio stream
elif key == "7":
    subscribe_audio_stream()
# 2.4 Unsubscribe from audio stream
elif key.upper() == "8":
    unsubscribe_audio_stream()
# 3. Wakeup Status Functions
# 3.1 Open wakeup status stream
elif key.upper() == "Q":
    open_wakeup_status_stream()
# 3.2 Close wakeup status stream
elif key.upper() == "W":
    close_wakeup_status_stream()
```

(continues on next page)

(continued from previous page)

```

        # 3.3 Subscribe to wakeup status stream
        elif key.upper() == "E":
            subscribe_wakeup_status()

        # 3.4 Unsubscribe from wakeup status stream
        elif key.upper() == "R":
            unsubscribe_wakeup_status()

        # 4. Print help information
        elif key.upper() == "?":
            print_help()

        else:
            logging.warning("Unknown key: %s", key)

        time.sleep(0.01) # Brief delay

    except KeyboardInterrupt:
        break
    except Exception as e:
        logging.error("Exception occurred while processing user input: %s", e)
except Exception as e:
    logging.error("Exception occurred during program execution: %s", e)
    return -1

finally:
    # Clean up resources
    try:
        logging.info("Clean up resources")
        # Close sensor controller
        audio_controller = robot.get_audio_controller()
        audio_controller.shutdown()
        logging.info("Audio controller closed")

        # Disconnect
        robot.disconnect()
        logging.info("Robot connection disconnected")

        # Shutdown robot
        robot.shutdown()
        logging.info("Robot shutdown")

    except Exception as e:

```

(continues on next page)

(continued from previous page)

```
logging.error("Exception occurred while cleaning up resources: %s", e)

if __name__ == "__main__":
    sys.exit(main())
```

## 24.3 Running Instructions

### 24.3.1 Environment Setup

```
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH
```

### 24.3.2 Run Example

```
# C++
./audio_example

# Python
python3 audio_example.py
```

### 24.3.3 Control Instructions

- 1: Get current volume
- 2: Set volume
- 3: Play TTS speech
- 4: Stop TTS playback
- 5: Open audio stream
- 6: Close audio stream
- 7: Subscribe to audio stream data
- 8: Unsubscribe from audio stream data
- Q: Open voice wakeup status stream
- W: Close voice wakeup status stream
- E: Subscribe to voice wakeup status
- R: Unsubscribe from voice wakeup status
- ?: Print help information

### 24.3.4 Stop Program

- Press `ESC` to safely stop the program
- The program will automatically clean up all resources

---

## State Monitor Example

---

---

This example demonstrates how to use the Magicbot-Z1 SDK for initialization, robot connection, robot status monitoring (faults, BMS), and other basic operations.

### 25.1 C++

Example file: `monitor_example.cpp`

```
#include "magic_robot.h"
#include "magic_sdk_version.h"

#include <unistd.h>
#include <csignal>

#include <iostream>

using namespace magic::z1;

magic::z1::MagicRobot robot;

void signalHandler(int signum) {
    std::cout << "Interrupt signal (" << signum << ") received.\n";
}
```

(continues on next page)

(continued from previous page)

```

robot.Shutdown();
// Exit process
exit(signum);
}

int main() {
    // Bind SIGINT (Ctrl+C)
    signal(SIGINT, signalHandler);

    std::cout << "SDK Version: " << SDK_VERSION_STRING << std::endl;

    std::string local_ip = "192.168.54.111";
    // Configure local IP address for direct ethernet connection to robot and
    ↪ initialize SDK
    if (!robot.Initialize(local_ip)) {
        std::cerr << "robot sdk initialize failed." << std::endl;
        robot.Shutdown();
        return -1;
    }

    // Connect to robot
    auto status = robot.Connect();
    if (status.code != ErrorCode::OK) {
        std::cerr << "connect robot failed"
            << ", code: " << status.code
            << ", message: " << status.message << std::endl;
        robot.Shutdown();
        return -1;
    }

    // Wait for 5 seconds
    usleep(5000000);

    auto& monitor = robot.GetStateMonitor();

    RobotState state;
    status = monitor.GetCurrentState(state);
    if (status.code != ErrorCode::OK) {
        std::cerr << "get robot state failed"
            << ", code: " << status.code
            << ", message: " << status.message << std::endl;
    }
}

```

(continues on next page)

(continued from previous page)

```

robot.Shutdown();
return -1;
}

std::cout << "health: " << state.bms_data.battery_health
    << ", percentage: " << state.bms_data.battery_percentage
    << ", state: " << std::to_string((int8_t) state.bms_data.battery_state)
    << ", power_supply_status: " << std::to_string((int8_t) state.bms_data.
↪power_supply_status)
    << std::endl;

auto& faults = state.faults;
for (auto& [code, msg] : faults) {
    std::cout << "code: " << std::to_string(code)
        << ", message: " << msg << std::endl;
}

// Disconnect from robot
status = robot.Disconnect();
if (status.code != ErrorCode::OK) {
    std::cerr << "disconnect robot failed"
        << ", code: " << status.code
        << ", message: " << status.message << std::endl;

    robot.Shutdown();
    return -1;
}

robot.Shutdown();

return 0;
}

```

## 25.2 Python

Example file: monitor\_example.py

```

#!/usr/bin/env python3

import sys
import time

```

(continues on next page)

(continued from previous page)

```

import signal
import logging
from typing import Optional

import magicbot_z1_python as magicbot

# Configure logging format and level
logging.basicConfig(
    level=logging.INFO, # Minimum log level
    format="%(asctime)s [%(levelname)s] %(message)s",
    datefmt="%Y-%m-%d %H:%M:%S",
)

# Global variables
robot: Optional[magicbot.MagicRobot] = None

def signal_handler(signum, frame):
    """Signal handler function for graceful exit"""
    global robot
    logging.info("Received interrupt signal (%s), exiting...", signum)
    if robot:
        robot.disconnect()
        logging.info("Robot disconnected")
        robot.shutdown()
        logging.info("Robot shutdown")
    exit(-1)

def main():
    """Main function"""
    global robot

    # Bind signal handler
    signal.signal(signal.SIGINT, signal_handler)

    logging.info("Robot model: %s", magicbot.get_robot_model())

    # Create robot instance

```

(continues on next page)



(continued from previous page)

```
robot = magicbot.MagicRobot()

try:
    # Configure local IP address for direct network connection and initialize SDK
    local_ip = "192.168.54.111"
    if not robot.initialize(local_ip):
        logging.error("Failed to initialize robot SDK")
        robot.shutdown()
        return -1

    # Connect to robot
    status = robot.connect()
    if status.code != magicbot.ErrorCode.OK:
        logging.error(
            "Failed to connect to robot, code: %s, message: %s",
            status.code,
            status.message,
        )
        robot.shutdown()
        return -1

    logging.info("Successfully connected to robot")

    # Wait 5 seconds
    logging.info("Waiting 5 seconds...")
    time.sleep(5)

    # Get state monitor
    monitor = robot.get_state_monitor()

    # Get current state
    state = monitor.get_current_state()

    # Print battery information
    logging.info("Battery health: %s", state.bms_data.battery_health)
    logging.info("Battery percentage: %s%%", state.bms_data.battery_percentage)
    logging.info("Battery state: %s", state.bms_data.battery_state)
    logging.info("Power supply status: %s", state.bms_data.power_supply_status)

    # Print fault information
```

(continues on next page)

(continued from previous page)

```
faults = state.faults
for fault in faults:
    logging.info(
        "Error code: %s, Error message: %s",
        fault.error_code,
        fault.error_message,
    )

except Exception as e:
    logging.error("Exception occurred during program execution: %s", e)
    return -1

finally:
    # Clean up resources
    try:
        logging.info("Clean up resources")
        # Close state monitor
        monitor = robot.get_state_monitor()
        monitor.shutdown()

        # Disconnect
        robot.disconnect()
        logging.info("Robot connection disconnected")

        # Shutdown robot
        robot.shutdown()
        logging.info("Robot shutdown")

    except Exception as e:
        logging.error("Exception occurred while cleaning up resources: %s", e)

if __name__ == "__main__":
    sys.exit(main())
```

## 25.3 Running Instructions

### 25.3.1 Environment Setup

```
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH
```

### 25.3.2 Run Example

```
# C++
./monitor_example
# Python
python3 monitor_example.py
```

### 25.3.3 Stop Program

- Press `Ctrl+C` to safely stop the program
- The program will automatically clean up all resources



---

## SLAM Navigation Example

---

---

This example demonstrates how to use the Magicbot-Z1 SDK for SLAM mapping, localization, navigation and other operations, including map management, pose acquisition and other functions.

### 26.1 C++

Example files:

- `slam_example.cpp`
- `navigation_example.cpp`

Reference documentation:

- C++ `API/slam_navigation_reference.md`

#### 26.1.1 Mapping Example

```
#include "magic_robot.h"
#include "magic_sdk_version.h"

#include <termios.h>
#include <unistd.h>
#include <csignal>
#include <ctime>
```

(continues on next page)

(continued from previous page)

```
#include <fstream>
#include <iostream>
#include <string>

using namespace magic::z1;

magic::z1::MagicRobot robot;
bool running = true;
SlamMode current_slam_mode = SlamMode::IDLE;

void SignalHandler(int signum) {
    std::cout << "Received interrupt signal (" << signum << "), exiting..." << \n;
    std::endl;
    running = false;
    robot.Shutdown();
    exit(signum);
}

void PrintHelp() {
    std::cout << "\n===== " << std::endl;
    std::cout << "SLAM and Navigation Function Demo Program" << std::endl;
    std::cout << "===== " << std::endl;
    std::cout << "preparation Functions:" << std::endl;
    std::cout << "  0      Function 0: Recovery stand" << std::endl;
    std::cout << "SLAM Functions:" << std::endl;
    std::cout << "  1      Function 1: Switch to mapping mode" << std::endl;
    std::cout << "  2      Function 2: Start mapping" << std::endl;
    std::cout << "  3      Function 3: Cancel mapping" << std::endl;
    std::cout << "  4      Function 4: Save map" << std::endl;
    std::cout << "  5      Function 5: Load map (input map name after pressing 5)" << \n;
    std::endl;
    std::cout << "  6      Function 6: Delete map (input map name after pressing 6)" <
    < std::endl;
    std::cout << "  7      Function 7: Get all map information and save map image as \n
    PGM file" << std::endl;
    std::cout << "  8      Function 8: Get map path (input map name)" << std::endl;
    std::cout << "  9      Function 9: Get SLAM mapping point cloud map" << std::endl;
    std::cout << "Close Functions:" << std::endl;
    std::cout << "  P      Function P: Close SLAM" << std::endl;
    std::cout << "\n ?      Function ?: Print help" << std::endl;
```

(continues on next page)

(continued from previous page)

```
std::cout << "   ESC       Exit program" << std::endl;
std::cout << "=====\\n"
    << std::endl;
}

int getch() {
    struct termios oldt, newt;
    int ch;
    tcgetattr(STDIN_FILENO, &oldt);
    newt = oldt;
    newt.c_lflag &= ~(ICANON | ECHO);
    tcsetattr(STDIN_FILENO, TCSANOW, &newt);
    ch = getchar();
    tcsetattr(STDIN_FILENO, TCSANOW, &oldt);
    return ch;
}

std::string GetUserInput(const std::string& prompt) {
    std::cout << prompt;
    std::string input;
    std::getline(std::cin, input);
    return input;
}

void RecoveryStand() {
    std::cout << "=== Executing Recovery Stand ===" << std::endl;
    auto& controller = robot.GetHighLevelMotionController();

    auto status = controller.SetGait(GaitMode::GAIT_RECOVERY_STAND, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to set robot gait, code: " << status.code
            << ", message: " << status.message << std::endl;
        return;
    }
    std::cout << "Successfully executed recovery stand" << std::endl;
}

void SwitchToMappingMode() {
    auto& controller = robot.GetSlamNavController();
```

(continues on next page)

(continued from previous page)

```

    auto status = controller.ActivateSlamMode(SlamMode::MAPPING, "", 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to switch to mapping mode, code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }

    current_slam_mode = SlamMode::MAPPING;
    std::cout << "Successfully switched to mapping mode" << std::endl;
    std::cout << "Robot is now in mapping mode, ready to create new maps" << std::endl;
}

void StartMapping() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.StartMapping(10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to start mapping, code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }

    std::cout << "Successfully started mapping" << std::endl;
}

void CancelMapping() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.CancelMapping(10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to cancel mapping, code: " << status.code
                    << ", message: " << status.message << std::endl;

        return;
    }

    std::cout << "Successfully cancelled mapping" << std::endl;
}

void SaveMap() {
    auto& controller = robot.GetSlamNavController();

```

(continues on next page)



(continued from previous page)

```

    if (current_slam_mode != SlamMode::MAPPING) {
        std::cerr << "Warning: Currently not in mapping mode, may not be able to save map
↪" << std::endl;
    }

    // Generate map name with timestamp
    std::time_t now = std::time(nullptr);
    std::string map_name = "map_" + std::to_string(now);
    std::cout << "Saving map: " << map_name << std::endl;

    auto status = controller.SaveMap(map_name, 20000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to save map, code: " << status.code
            << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully saved map: " << map_name << std::endl;
}

void LoadMap(const std::string& map_name) {
    if (map_name.empty()) {
        std::cerr << "Map to load is not provided" << std::endl;
        return;
    }

    auto& controller = robot.GetSlamNavController();

    std::cout << "Loading map: " << map_name << std::endl;
    auto status = controller.LoadMap(map_name, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to load map, code: " << status.code
            << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully loaded map: " << map_name << std::endl;
}

```

(continues on next page)

(continued from previous page)

```
void DeleteMap(const std::string& map_name) {
    if (map_name.empty()) {
        std::cerr << "Map to delete is not provided" << std::endl;
        return;
    }

    auto& controller = robot.GetSlamNavController();

    std::cout << "Deleting map: " << map_name << std::endl;
    auto status = controller.DeleteMap(map_name, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to delete map, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully deleted map: " << map_name << std::endl;
}

void SaveMapImageToFile(const MapInfo& map_info) {
    try {
        const auto& map_data = map_info.map_meta_data.map_image_data;
        uint32_t width = map_data.width;
        uint32_t height = map_data.height;
        uint32_t max_gray_value = map_data.max_gray_value;
        const auto& image_bytes = map_data.image;

        std::cout << "Saving map image: " << width << "x" << height
                    << ", max_gray: " << max_gray_value << std::endl;

        // Check image data size
        if (image_bytes.size() != width * height) {
            std::cerr << "Image data size mismatch: expected " << (width * height)
                        << ", got " << image_bytes.size() << std::endl;
            return;
        }

        // Generate filename based on map name
        std::string safe_filename = map_info.map_name;
        // Remove invalid characters
```

(continues on next page)

(continued from previous page)

```

safe_filename.erase(
    std::remove_if(safe_filename.begin(), safe_filename.end(),
        [](char c) { return !std::isalnum(c) && c != '_' && c != '-'; }
    ),
    safe_filename.end());

if (safe_filename.empty()) {
    safe_filename = "map_" + std::to_string(std::time(nullptr));
}

// Save as PGM format
std::string pgm_filename = "build/" + safe_filename + ".pgm";
std::ofstream pgm_file(pgm_filename, std::ios::binary);
if (!pgm_file.is_open()) {
    std::cerr << "Failed to open file for writing: " << pgm_filename << std::endl;
    return;
}

// Write PGM header
pgm_file << "P5\n"
    << width << " " << height << "\n"
    << max_gray_value << "\n";

// Write image data
pgm_file.write(reinterpret_cast<const char*>(image_bytes.data()), image_bytes.
    size());
pgm_file.close();

std::cout << "Map image saved successfully as PGM: " << pgm_filename << std::endl;

} catch (const std::exception& e) {
    std::cerr << "Exception occurred while saving map image: " << e.what() <<
    std::endl;
}
}

void GetAllMapInfo() {
    auto& controller = robot.GetSlamNavController();

    AllMapInfo all_map_info;

```

(continues on next page)

(continued from previous page)

```

auto status = controller.GetAllMapInfo(all_map_info, 10000);
if (status.code != ErrorCode::OK) {
    std::cerr << "Failed to get map information, code: " << status.code
                << ", message: " << status.message << std::endl;
    return;
}

std::cout << "Successfully retrieved map information" << std::endl;
std::cout << "Current map: " << all_map_info.current_map_name << std::endl;
std::cout << "Total maps: " << all_map_info.map_infos.size() << std::endl;

if (!all_map_info.map_infos.empty()) {
    std::cout << "Map details:" << std::endl;
    for (size_t i = 0; i < all_map_info.map_infos.size(); ++i) {
        const auto& map_info = all_map_info.map_infos[i];
        std::cout << "  Map " << (i + 1) << ": " << map_info.map_name << std::endl;
        std::cout << "    Origin: [" << map_info.map_meta_data.origin.position[0] << ",
↪"
                                << map_info.map_meta_data.origin.position[1] << ", "
                                << map_info.map_meta_data.origin.position[2] << "]" << std::endl;
        std::cout << "    Orientation: [" << map_info.map_meta_data.origin.
↪orientation[0] << ", "
                                << map_info.map_meta_data.origin.orientation[1] << ", "
                                << map_info.map_meta_data.origin.orientation[2] << "]" << std::endl;
        std::cout << "    Resolution: " << map_info.map_meta_data.resolution << " m/
↪pixel" << std::endl;
        std::cout << "    Size: " << map_info.map_meta_data.map_image_data.width << " x
↪"
                                << map_info.map_meta_data.map_image_data.height << std::endl;
        std::cout << "    Max gray value: " << map_info.map_meta_data.map_image_data.
↪max_gray_value << std::endl;
        std::cout << "    Image type: " << map_info.map_meta_data.map_image_data.type <
↪< std::endl;

        SaveMapImageToFile(map_info);
    }
} else {
    std::cout << "No available maps" << std::endl;
}
}

```

(continues on next page)

(continued from previous page)

```

void GetMapPath(const std::string& map_name) {
    if (map_name.empty()) {
        std::cerr << "Map to get path is not provided" << std::endl;
        return;
    }

    auto& controller = robot.GetSlamNavController();

    std::vector<std::string> map_path;
    auto status = controller.GetMapPath(map_name, map_path, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to get map path, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    if (map_path.empty()) {
        std::cerr << "No map path found" << std::endl;
        return;
    }

    for (const auto& path : map_path) {
        std::cout << "Map path: " << path << std::endl;
    }
}

void GetPointCloudMap() {
    auto& controller = robot.GetSlamNavController();

    PointCloud2 point_cloud_map;
    auto status = controller.GetPointCloudMap(point_cloud_map, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to get SLAM mapping point cloud map, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully got SLAM mapping point cloud map" << std::endl;
    std::cout << "Point cloud map - Height: " << point_cloud_map.height

```

(continues on next page)

(continued from previous page)

```

        << " , Width: " << point_cloud_map.width << std::endl;
    std::cout << "Point cloud map data size: " << point_cloud_map.data.size() << " bytes
    ↪" << std::endl;
}

void CloseSlam() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.ActivateSlamMode(SlamMode::IDLE, "", 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to close SLAM, code: " << status.code
            << " , message: " << status.message << std::endl;
        return;
    }

    current_slam_mode = SlamMode::IDLE;
    std::cout << "Successfully closed SLAM system" << std::endl;
}

int main(int argc, char* argv[]) {
    // Bind signal handler
    signal(SIGINT, SignalHandler);

    std::cout << "\n===== " << std::endl;
    std::cout << "MagicBot Z1 SDK SLAM Example" << std::endl;
    std::cout << "SDK Version: " << SDK_VERSION_STRING << std::endl;
    std::cout << "=====\n"
        << std::endl;

    PrintHelp();
    std::cout << "Press any key to continue (ESC to exit)..." << std::endl;

    // Configure local IP address for direct network connection and initialize SDK
    std::string local_ip = "192.168.54.111";
    if (!robot.Initialize(local_ip)) {
        std::cerr << "Failed to initialize robot SDK" << std::endl;
        robot.Shutdown();
        return -1;
    }
}

```

(continues on next page)

(continued from previous page)

```
// Connect to robot
auto status = robot.Connect();
if (status.code != ErrorCode::OK) {
    std::cerr << "Failed to connect to robot, code: " << status.code
                << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}
std::cout << "Successfully connected to robot" << std::endl;

// Switch motion control controller to high-level controller
status = robot.SetMotionControlLevel(ControllerLevel::HighLevel);
if (status.code != ErrorCode::OK) {
    std::cerr << "Failed to switch robot motion control level, code: " << status.code
                << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}

// Initialize SLAM navigation controller
auto& slam_nav_controller = robot.GetSlamNavController();
if (!slam_nav_controller.Initialize()) {
    std::cerr << "Failed to initialize SLAM navigation controller" << std::endl;
    robot.Disconnect();
    robot.Shutdown();
    return -1;
}
std::cout << "Successfully initialized SLAM navigation controller" << std::endl;

// Main loop
while (running) {
    int key = getch();

    if (key == 27) { // ESC key
        std::cout << "ESC key pressed, exiting..." << std::endl;
        break;
    }

    switch (key) {
        case '0':
```

(continues on next page)

(continued from previous page)

```

    RecoveryStand();
    break;
case '1':
    SwitchToMappingMode();
    break;
case '2':
    StartMapping();
    break;
case '3':
    CancelMapping();
    break;
case '4':
    SaveMap();
    break;
case '5': {
    std::string map_name = GetUserInput("Enter map name to load: ");
    LoadMap(map_name);
    break;
}
case '6': {
    std::string map_name = GetUserInput("Enter map name to delete: ");
    DeleteMap(map_name);
    break;
}
case '7':
    GetAllMapInfo();
    break;
case '8': {
    std::string map_name = GetUserInput("Enter map name to get path: ");
    GetMapPath(map_name);
    break;
}
case '9':
    GetPointCloudMap();
    break;
case 'p':
case 'P':
    CloseSlam();
    break;
case '?':

```

(continues on next page)



(continued from previous page)

```

        PrintHelp();
        break;
    default:
        std::cout << "Unknown key: " << static_cast<char>(key) << std::endl;
        break;
    }

    usleep(10000); // 10ms delay
}

// Cleanup resources
std::cout << "Clean up resources" << std::endl;

slam_nav_controller.Shutdown();
std::cout << "SLAM navigation controller closed" << std::endl;

robot.Disconnect();
std::cout << "Robot connection disconnected" << std::endl;

robot.Shutdown();
std::cout << "Robot shutdown" << std::endl;

return 0;
}

```

### 26.1.2 Navigation Example

```

#include "magic_robot.h"
#include "magic_sdk_version.h"

#include <termios.h>
#include <unistd.h>
#include <atomic>
#include <csignal>
#include <ctime>
#include <iostream>
#include <sstream>
#include <string>

using namespace magic::z1;

```

(continues on next page)

(continued from previous page)

```

magic::z1::MagicRobot robot;
bool running = true;
SlamMode current_slam_mode = SlamMode::IDLE;
NavMode current_nav_mode = NavMode::IDLE;
std::atomic<int> odometry_counter{0};

void SignalHandler(int signum) {
    std::cout << "Received interrupt signal (" << signum << "), exiting..." << \n
    std::endl;
    running = false;
    robot.Shutdown();
    exit(signum);
}

void PrintHelp() {
    std::cout << "\n===== " << std::endl;
    std::cout << "SLAM and Navigation Function Demo Program" << std::endl;
    std::cout << "===== " << std::endl;
    std::cout << "\npreparation Functions:" << std::endl;
    std::cout << "  Q      Function Q: Recovery stand" << std::endl;
    std::cout << "  W      Function W: Balance stand" << std::endl;
    std::cout << "  E      Function E: Get map path (input map name)" << std::endl;
    std::cout << "\nLocalization Functions:" << std::endl;
    std::cout << "  1      Function 1: Switch to localization mode (input map path)" <
    std::endl;
    std::cout << "  2      Function 2: Initialize pose (input x y yaw)" << std::endl;
    std::cout << "  3      Function 3: Get current pose information" << std::endl;
    std::cout << "\nNavigation Functions:" << std::endl;
    std::cout << "  4      Function 4: Switch to navigation mode (input map path)" << \n
    std::endl;
    std::cout << "  5      Function 5: Set navigation target goal (input x y yaw)" << \n
    std::endl;
    std::cout << "  6      Function 6: Pause navigation" << std::endl;
    std::cout << "  7      Function 7: Resume navigation" << std::endl;
    std::cout << "  8      Function 8: Cancel navigation" << std::endl;
    std::cout << "  9      Function 9: Get navigation status" << std::endl;
    std::cout << "\nOdometry Functions:" << std::endl;
    std::cout << "  Z      Function Z: Open odometry stream" << std::endl;
    std::cout << "  X      Function X: Close odometry stream" << std::endl;

```

(continues on next page)

(continued from previous page)

```

std::cout << "  C      Function C: Subscribe odometry stream" << std::endl;
std::cout << "  V      Function V: Unsubscribe odometry stream" << std::endl;
std::cout << "\nClose Functions:" << std::endl;
std::cout << "  P      Function P: Close SLAM" << std::endl;
std::cout << "  L      Function L: Close navigation" << std::endl;
std::cout << "\n  ?      Function ?: Print help" << std::endl;
std::cout << "  ESC    Exit program" << std::endl;
std::cout << "=====\\n"
        << std::endl;
}

int getch() {
    struct termios oldt, newt;
    int ch;
    tcgetattr(STDIN_FILENO, &oldt);
    newt = oldt;
    newt.c_lflag &= ~(ICANON | ECHO);
    tcsetattr(STDIN_FILENO, TCSANOW, &newt);
    ch = getchar();
    tcsetattr(STDIN_FILENO, TCSANOW, &oldt);
    return ch;
}

std::string GetUserInput(const std::string& prompt) {
    std::cout << prompt;
    std::string input;
    std::getline(std::cin, input);
    return input;
}

void RecoveryStand() {
    std::cout << "=== Executing Recovery Stand ===" << std::endl;
    auto& controller = robot.GetHighLevelMotionController();

    auto status = controller.SetGait(GaitMode::GAIT_RECOVERY_STAND, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to set robot gait, code: " << status.code
            << ", message: " << status.message << std::endl;
        return;
    }
}

```

(continues on next page)

(continued from previous page)

```

    std::cout << "Successfully executed recovery stand" << std::endl;
}

void BalanceStand() {
    std::cout << "=== Executing Balance Stand ===" << std::endl;
    auto& controller = robot.GetHighLevelMotionController();

    auto status = controller.SetGait(GaitMode::GAIT_BALANCE_STAND, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to set robot gait, code: " << status.code
            << ", message: " << status.message << std::endl;
        return;
    }
    std::cout << "Successfully executed balance stand" << std::endl;
}

void GetMapPath(const std::string& map_name) {
    if (map_name.empty()) {
        std::cerr << "Map to get path is not provided" << std::endl;
        return;
    }

    auto& controller = robot.GetSlamNavController();

    std::vector<std::string> map_path;
    auto status = controller.GetMapPath(map_name, map_path, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to get map path, code: " << status.code
            << ", message: " << status.message << std::endl;
        return;
    }

    if (map_path.empty()) {
        std::cerr << "No map path found" << std::endl;
        return;
    }

    for (const auto& path : map_path) {
        std::cout << "Map path: " << path << std::endl;
    }
}

```

(continues on next page)

(continued from previous page)

```

}

void SwitchToLocalizationMode(const std::string& map_path) {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.ActivateSlamMode(SlamMode::LOCALIZATION, map_path, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to switch to localization mode, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    current_slam_mode = SlamMode::LOCALIZATION;
    std::cout << "Successfully switched to localization mode" << std::endl;
    std::cout << "Robot is now in localization mode, ready to localize on existing maps
    ↪" << std::endl;
}

void InitializePose(double x, double y, double yaw) {
    auto& controller = robot.GetSlamNavController();

    Pose3DEuler initial_pose;
    initial_pose.position = {x, y, 0.0};
    initial_pose.orientation = {0.0, 0.0, yaw};

    std::cout << "Initializing robot pose to: [" << x << ", " << y << ", " << yaw << "]"
    ↪" << std::endl;

    auto status = controller.InitPose(initial_pose, 15000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to initialize pose, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully initialized pose" << std::endl;
    std::cout << "Robot pose has been set to [" << x << ", " << y << ", " << yaw << "]"
    ↪<< std::endl;
}

```

(continues on next page)

(continued from previous page)

```

void GetCurrentPoseInfo() {
    auto& controller = robot.GetSlamNavController();

    LocalizationInfo pose_info;
    auto status = controller.GetCurrentLocalizationInfo(pose_info);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to get current pose information, code: " << status.code
            << ", message: " << status.message << std::endl;

        return;
    }

    std::cout << "Successfully retrieved current pose information" << std::endl;
    std::cout << "Localization status: " << (pose_info.is_localization ? "Localized" :
    ↪ "Not localized") << std::endl;

    std::cout << "Position: [" << pose_info.pose.position[0] << ", "
        << pose_info.pose.position[1] << ", "
        << pose_info.pose.position[2] << "]" << std::endl;
    std::cout << "Orientation: [" << pose_info.pose.orientation[0] << ", "
        << pose_info.pose.orientation[1] << ", "
        << pose_info.pose.orientation[2] << "]" << std::endl;
}

void SwitchToNavigationMode(const std::string& map_path) {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.ActivateNavMode(NavMode::GRID_MAP, map_path, 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to switch to navigation mode, code: " << status.code
            << ", message: " << status.message << std::endl;

        return;
    }

    current_nav_mode = NavMode::GRID_MAP;
    std::cout << "Successfully switched to navigation mode" << std::endl;
}

void SetNavigationTarget(double x, double y, double yaw) {
    auto& controller = robot.GetSlamNavController();

    NavTarget target_goal;

```

(continues on next page)

(continued from previous page)

```
target_goal.id = 1;
target_goal.frame_id = "map";
target_goal.goal.position = {x, y, 0.0};
target_goal.goal.orientation = {0.0, 0.0, yaw};

auto status = controller.SetNavTarget(target_goal, 10000);
if (status.code != ErrorCode::OK) {
    std::cerr << "Failed to set navigation target, code: " << status.code
                << ", message: " << status.message << std::endl;
    return;
}

std::cout << "Successfully set navigation target: position=(" << x << ", " << y <<
↪", 0.0), "
                << "orientation=(0.0, 0.0, " << yaw << ")" << std::endl;
}

void PauseNavigation() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.PauseNavTask();
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to pause navigation, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully paused navigation" << std::endl;
}

void ResumeNavigation() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.ResumeNavTask();
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to resume navigation, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }
}
```

(continues on next page)

(continued from previous page)

```

    std::cout << "Successfully resumed navigation" << std::endl;
}

void CancelNavigation() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.CancelNavTask();
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to cancel navigation, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully cancelled navigation" << std::endl;
}

void GetNavigationStatus() {
    auto& controller = robot.GetSlamNavController();

    NavStatus nav_status;
    auto status = controller.GetNavTaskStatus(nav_status);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to get navigation status, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "=== Navigation Status ===" << std::endl;
    std::cout << "Target ID: " << nav_status.id << std::endl;
    std::cout << "Status: " << static_cast<int>(nav_status.status) << std::endl;
    std::cout << "Error code: " << nav_status.error_code << std::endl;
    std::cout << "Error description: " << nav_status.error_desc << std::endl;

    // Status interpretation
    std::string status_meaning;
    switch (nav_status.status) {
        case NavStatusType::NONE:
            status_meaning = "No navigation target set";
            break;
        case NavStatusType::RUNNING:

```

(continues on next page)



(continued from previous page)

```

        status_meaning = "Navigation is running";
        break;
    case NavStatusType::END_SUCCESS:
        status_meaning = "Navigation completed successfully";
        break;
    case NavStatusType::END_FAILED:
        status_meaning = "Navigation failed";
        break;
    case NavStatusType::PAUSE:
        status_meaning = "Navigation is paused";
        break;
    case NavStatusType::CONTINUE:
        status_meaning = "Navigation resumed from pause";
        break;
    case NavStatusType::CANCEL:
        status_meaning = "Navigation was cancelled";
        break;
    default:
        status_meaning = "Unknown status";
        break;
}

std::cout << "Status meaning: " << status_meaning << std::endl;
std::cout << "=====" << std::endl;
}

void OpenOdometryStream() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.OpenOdometryStream();
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to open odometry stream, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully opened odometry stream" << std::endl;
}

void CloseOdometryStream() {

```

(continues on next page)

(continued from previous page)

```

    auto& controller = robot.GetSlamNavController();

    auto status = controller.CloseOdometryStream();
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to close odometry stream, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    std::cout << "Successfully closed odometry stream" << std::endl;
}

void SubscribeOdometryStream() {
    auto& controller = robot.GetSlamNavController();

    auto callback = [](const std::shared_ptr<Odometry> odometry) {
        if (odometry_counter % 30 == 0) {
            std::cout << "Odometry position: " << odometry->position[0] << ", "
                        << odometry->position[1] << ", " << odometry->position[2] << "\n";
            std::cout << "Odometry orientation: " << odometry->orientation[0] << ", "
                        << odometry->orientation[1] << ", " << odometry->orientation[2] << ", "
                        << odometry->orientation[3] << std::endl;
            std::cout << "Odometry linear velocity: " << odometry->linear_velocity[0] << ", "
                        << odometry->linear_velocity[1] << ", " << odometry->linear_
velocity[2] << std::endl;
            std::cout << "Odometry angular velocity: " << odometry->angular_velocity[0] <<
                        << ", "
                        << odometry->angular_velocity[1] << ", " << odometry->angular_
velocity[2] << std::endl;
        }
        odometry_counter++;
    };

    controller.SubscribeOdometry(callback);
    std::cout << "Successfully subscribed odometry stream" << std::endl;
}

```

(continues on next page)

(continued from previous page)

```
void UnsubscribeOdometryStream() {
    auto& controller = robot.GetSlamNavController();

    controller.UnsubscribeOdometry();
    std::cout << "Successfully unsubscribed odometry stream" << std::endl;
}

void CloseSlam() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.ActivateSlamMode(SlamMode::IDLE, "", 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to close SLAM, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    current_slam_mode = SlamMode::IDLE;
    std::cout << "Successfully closed SLAM system" << std::endl;
}

void CloseNavigation() {
    auto& controller = robot.GetSlamNavController();

    auto status = controller.ActivateNavMode(NavMode::IDLE, "", 10000);
    if (status.code != ErrorCode::OK) {
        std::cerr << "Failed to close navigation, code: " << status.code
                    << ", message: " << status.message << std::endl;
        return;
    }

    current_nav_mode = NavMode::IDLE;
    std::cout << "Successfully closed navigation system" << std::endl;
}

int main(int argc, char* argv[]) {
    // Bind signal handler
    signal(SIGINT, SignalHandler);

    std::cout << "\n===== " << std::endl;
```

(continues on next page)

(continued from previous page)

```
std::cout << "MagicBot Z1 SDK Navigation Example" << std::endl;
std::cout << "SDK Version: " << SDK_VERSION_STRING << std::endl;
std::cout << "=====\n"
    << std::endl;

PrintHelp();
std::cout << "Press any key to continue (ESC to exit)..." << std::endl;

// Configure local IP address for direct network connection and initialize SDK
std::string local_ip = "192.168.54.111";
if (!robot.Initialize(local_ip)) {
    std::cerr << "Failed to initialize robot SDK" << std::endl;
    robot.Shutdown();
    return -1;
}

// Connect to robot
auto status = robot.Connect();
if (status.code != ErrorCode::OK) {
    std::cerr << "Failed to connect to robot, code: " << status.code
        << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}
std::cout << "Successfully connected to robot" << std::endl;

// Switch motion control controller to high-level controller
status = robot.SetMotionControlLevel(ControllerLevel::HighLevel);
if (status.code != ErrorCode::OK) {
    std::cerr << "Failed to switch robot motion control level, code: " << status.code
        << ", message: " << status.message << std::endl;
    robot.Shutdown();
    return -1;
}
std::cout << "Successfully switched robot motion control level to high-level" <<
std::endl;

// Initialize SLAM navigation controller
auto& slam_nav_controller = robot.GetSlamNavController();
if (!slam_nav_controller.Initialize()) {
```

(continues on next page)

(continued from previous page)

```
std::cerr << "Failed to initialize SLAM navigation controller" << std::endl;
robot.Disconnect();
robot.Shutdown();
return -1;
}
std::cout << "Successfully initialized SLAM navigation controller" << std::endl;

// Main loop
while (running) {
    int key = getch();

    if (key == 27) { // ESC key
        std::cout << "ESC key pressed, exiting..." << std::endl;
        break;
    }

    switch (key) {
        // 1. preparation Functions
        case 'q':
        case 'Q':
            RecoveryStand();
            break;
        case 'w':
        case 'W':
            BalanceStand();
            break;

        case 'e':
        case 'E': {
            std::string map_name = GetUserInput("Enter map name to get path: ");
            GetMapPath(map_name);
            break;
        }

        // 2. Localization Functions
        case '1': {
            std::string map_path = GetUserInput("Enter map path for localization: ");
            SwitchToLocalizationMode(map_path);
            break;
        }

        case '2': {
```

(continues on next page)

(continued from previous page)

```

        std::string input = GetUserInput("Enter pose (x y yaw): ");
        std::istringstream iss(input);
        double x = 0.0, y = 0.0, yaw = 0.0;
        iss >> x >> y >> yaw;
        std::cout << "input pose, x: " << x << ", y: " << y << ", yaw: " << yaw << "\n";
    }
    std::endl;

    InitializePose(x, y, yaw);
    break;
}

case '3':
    GetCurrentPoseInfo();
    break;

// 3. Navigation Functions

case '4': {
    std::string map_path = GetUserInput("Enter map path for navigation: ");
    SwitchToNavigationMode(map_path);
    break;
}

case '5': {
    std::string input = GetUserInput("Enter target (x y yaw): ");
    std::istringstream iss(input);
    double x = 0.0, y = 0.0, yaw = 0.0;
    iss >> x >> y >> yaw;
    SetNavigationTarget(x, y, yaw);
    break;
}

case '6':
    PauseNavigation();
    break;

case '7':
    ResumeNavigation();
    break;

case '8':
    CancelNavigation();
    break;

case '9':
    GetNavigationStatus();
    break;

// 4. Odometry Functions

```

(continues on next page)

(continued from previous page)

```

    case 'z':
    case 'Z':
        OpenOdometryStream();
        break;
    case 'x':
    case 'X':
        CloseOdometryStream();
        break;
    case 'c':
    case 'C':
        SubscribeOdometryStream();
        break;
    case 'v':
    case 'V':
        UnsubscribeOdometryStream();
        break;
    // 5. Close Functions
    case 'l':
    case 'L':
        CloseNavigation();
        break;
    case 'p':
    case 'P':
        CloseSlam();
        break;

    case '?':
        PrintHelp();
        break;
    default:
        std::cout << "Unknown key: " << static_cast<char>(key) << std::endl;
        break;
}

usleep(10000); // 10ms delay
}

// Cleanup resources
std::cout << "Clean up resources" << std::endl;

```

(continues on next page)

(continued from previous page)

```
slam_nav_controller.Shutdown();
std::cout << "SLAM navigation controller closed" << std::endl;

robot.Disconnect();
std::cout << "Robot connection disconnected" << std::endl;

robot.Shutdown();
std::cout << "Robot shutdown" << std::endl;

return 0;
}
```

## 26.2 Python

Example files:

- `slam_example.py`
- `navigation_example.py`

Reference documentation:

- `Python API/slam_navigation_reference.md`

### 26.2.1 Mapping Example

```
#!/usr/bin/env python3
# -*- coding: utf-8 -*-

import sys
import time
import signal
import threading
import logging
from typing import Optional
import numpy as np
import cv2
import random
import termios
import tty

import magicbot_z1_python as magicbot
```

(continues on next page)



(continued from previous page)

```
# Configure logging format and level
logging.basicConfig(
    level=logging.INFO, # Minimum log level
    format="%(asctime)s [%(levelname)s] %(message)s",
    datefmt="%Y-%m-%d %H:%M:%S",
)

# Global variables
robot: Optional[magicbot.MagicRobot] = None
running = True
current_slam_mode = None
current_nav_mode = magicbot.NavMode.IDLE

def signal_handler(signum, frame):
    """Signal handler function for graceful exit"""
    global running, robot
    logging.info("Received interrupt signal (%s), exiting...", signum)
    running = False
    if robot:
        robot.shutdown()
        logging.info("Robot shutdown")
    exit(-1)

def print_help():
    """Print help information"""
    logging.info("SLAM and Navigation Function Demo Program")
    logging.info("preparation Functions:")
    logging.info(" Q      Function Q: Recovery stand")
    logging.info(" E      Function E: Balance stand")
    logging.info(" W      Function W: Move forward")
    logging.info(" A      Function A: Move left")
    logging.info(" S      Function S: Move backward")
    logging.info(" D      Function D: Move right")
    logging.info(" X      Function X: Stop move")
    logging.info(" T      Function T: Turn left")
    logging.info(" G      Function G: Turn right")
    logging.info("")
```

(continues on next page)

(continued from previous page)

```

logging.info("SLAM Functions:")
logging.info(" 1      Function 1: Switch to mapping mode")
logging.info(" 2      Function 2: Start mapping")
logging.info(" 3      Function 3: Cancel mapping")
logging.info(" 4      Function 4: Save map")
logging.info(" 5      Function 5: Load map")
logging.info(" 6      Function 6: Delete map")
logging.info(
    " 7      Function 7: Get all map information and save map image as PGM file
↪ ")
)
logging.info(" 8      Function 8: Get map path")
logging.info(" 9      Function 9: Get SLAM mapping point cloud map")
logging.info("")
logging.info("Close Functions:")
logging.info(" P      Function P: Close SLAM")
logging.info("")
logging.info(" ?      Function ?: Print help")
logging.info(" ESC    Exit program")

# ===== SLAM Functions =====

def switch_to_mapping_mode():
    """Switch to mapping mode"""
    global robot, current_slam_mode
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Switch to mapping mode
        status = controller.activate_slam_mode(magicbot.SlamMode.MAPPING)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to switch to mapping mode, code: %s, message: %s",
                status.code,
                status.message,
            )
    return

```

(continues on next page)

(continued from previous page)

```

        current_slam_mode = "MAPPING"
        logging.info("Successfully switched to mapping mode")
        logging.info("Robot is now in mapping mode, ready to create new maps")
    except Exception as e:
        logging.error("Exception occurred while switching to mapping mode: %s", e)

def load_map(map_to_load):
    """Load map"""
    global robot
    try:
        if not map_to_load:
            logging.error("Map to load is not provided")
            return

        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        logging.info("Loading map: %s", map_to_load)
        controller.load_map(map_to_load)
    except Exception as e:
        logging.error("Exception occurred while loading map: %s", e)
        return

    logging.info("Successfully loaded map: %s", map_to_load)

def start_mapping():
    """Start mapping"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Start mapping
        status = controller.start_mapping()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to start mapping, code: %s, message: %s",
                status.code,

```

(continues on next page)

(continued from previous page)

```

        status.message,
    )
    return

    logging.info("Successfully started mapping")
except Exception as e:
    logging.error("Exception occurred while starting mapping: %s", e)

def cancel_mapping():
    """Cancel mapping"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Cancel mapping
        status = controller.cancel_mapping()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to cancel mapping, code: %s, message: %s",
                status.code,
                status.message,
            )
        return

        logging.info("Successfully cancelled mapping")
    except Exception as e:
        logging.error("Exception occurred while cancelling mapping: %s", e)

def save_map():
    """Save map"""
    global robot, current_slam_mode
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Check if in mapping mode
        if current_slam_mode != "MAPPING":

```

(continues on next page)

(continued from previous page)

```

        logging.warning(
            "Warning: Currently not in mapping mode, may not be able to save map"
        )

        # Generate map name with timestamp
        map_name = f"map_{int(time.time())}"
        logging.info("Saving map: %s", map_name)

        # Save map
        status = controller.save_map(map_name, 20000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to save map, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        logging.info("Successfully saved map: %s", map_name)
    except Exception as e:
        logging.error("Exception occurred while saving map: %s", e)

def delete_map(map_to_delete):
    """Delete map"""
    global robot
    try:
        if not map_to_delete:
            logging.error("Map to delete is not provided")
            return

        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Delete the first map as an example
        logging.info("Deleting map: %s", map_to_delete)

        # Delete map
        status = controller.delete_map(map_to_delete)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(

```

(continues on next page)

(continued from previous page)

```

        "Failed to delete map, code: %s, message: %s",
        status.code,
        status.message,
    )
    return

    logging.info("Successfully deleted map: %s", map_to_delete)
except Exception as e:
    logging.error("Exception occurred while deleting map: %s", e)

def get_all_map_info():
    """Get all map information"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Get all map information
        status, all_map_info = controller.get_all_map_info()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to get map information, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        logging.info("Successfully retrieved map information")
        logging.info("Current map: %s", all_map_info.current_map_name)
        logging.info("Total maps: %d", len(all_map_info.map_infos))

        if all_map_info.map_infos:
            logging.info("Map details:")
            for i, map_info in enumerate(all_map_info.map_infos):
                logging.info("  Map %d: %s", i + 1, map_info.map_name)
                logging.info(
                    "    Origin: [%f, %f, %f]",
                    map_info.map_meta_data.origin.position[0],
                    map_info.map_meta_data.origin.position[1],

```

(continues on next page)

(continued from previous page)

```

        map_info.map_meta_data.origin.position[2],
    )
    logging.info(
        "    Orientation: [%f, %f, %f]",
        map_info.map_meta_data.origin.orientation[0],
        map_info.map_meta_data.origin.orientation[1],
        map_info.map_meta_data.origin.orientation[2],
    )
    logging.info(
        "    Resolution: %f m/pixel", map_info.map_meta_data.resolution
    )
    logging.info(
        "    Size: %d x %d",
        map_info.map_meta_data.map_image_data.width,
        map_info.map_meta_data.map_image_data.height,
    )
    logging.info(
        "    Max gray value: %d",
        map_info.map_meta_data.map_image_data.max_gray_value,
    )
    logging.info(
        "    Image type: %s", map_info.map_meta_data.map_image_data.type
    )

    save_map_image_to_file(map_info)

else:
    logging.info("No available maps")
except Exception as e:
    logging.error("Exception occurred while getting map information: %s", e)

def save_map_image_to_file(map_info):
    """Save map image to current directory"""
    try:
        # Extract image data
        map_data = map_info.map_meta_data.map_image_data
        width = map_data.width
        height = map_data.height
        max_gray_value = map_data.max_gray_value

```

(continues on next page)

(continued from previous page)

```

image_bytes = map_data.image

logging.info(
    "Saving map image: %dx%d, max_gray: %d", width, height, max_gray_value
)

# Convert bytes to numpy array
if len(image_bytes) != width * height:
    logging.error(
        "Image data size mismatch: expected %d, got %d",
        width * height,
        len(image_bytes),
    )
    return

# Convert UInt8Vector to bytes for numpy processing
try:
    # Try to convert UInt8Vector to bytes
    if hasattr(image_bytes, "__iter__") and not isinstance(
        image_bytes, (str, bytes)
    ):
        # Convert UInt8Vector or similar iterable to bytes
        image_bytes_data = bytes(image_bytes)
    else:
        image_bytes_data = image_bytes
except Exception as e:
    logging.error("Failed to convert image data to bytes: %s", e)
    return

# Create numpy array from image data
image_array = np.frombuffer(image_bytes_data, dtype=np.uint8).reshape(
    (height, width)
)

# Generate filename based on map name
safe_filename = "".join(
    c for c in map_info.map_name if c.isalnum() or c in (" ", "-", "_")
).rstrip()
safe_filename = safe_filename.replace(" ", "_")
if not safe_filename:

```

(continues on next page)



(continued from previous page)

```

        safe_filename = f"map_{int(time.time())}"

        # Save as PGM format using OpenCV
        pgm_filename = f"build/{safe_filename}.pgm"
        success = cv2.imwrite(pgm_filename, image_array)

        if success:
            logging.info("Map image saved successfully as PGM: %s", pgm_filename)
        else:
            logging.error("Failed to save map image as PGM: %s", pgm_filename)

    except ImportError:
        logging.error("OpenCV not available, cannot save image")
        logging.info(
            "Image data: %dx%d pixels, %d bytes", width, height, len(image_bytes)
        )
    except Exception as e:
        logging.error("Exception occurred while saving map image: %s", e)

def get_map_path(map_to_get_path):
    """Get map path"""
    global robot
    try:
        if not map_to_get_path:
            logging.error("Map to get path is not provided")
            return

        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Get map path
        status, map_path = controller.get_map_path(map_to_get_path)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to get map path, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        if len(map_path) == 0:

```

(continues on next page)

(continued from previous page)

```

        logging.error("No map path found")
        return

    for path in map_path:
        logging.info("Map path: %s", path)
    except Exception as e:
        logging.error("Exception occurred while getting map path: %s", e)
        return

def get_point_cloud_map():
    """Get SLAM mapping point cloud map"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Get SLAM mapping point cloud map
        status, point_cloud_map = controller.get_point_cloud_map()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to get SLAM mapping point cloud map, code: %s, message: %s",
                status.code,
                status.message,
            )
            return
        logging.info("Successfully got SLAM mapping point cloud map")

        if point_cloud_map:
            logging.info(
                "Point cloud map - Height: %d, Width: %d, Data size: %d bytes",
                point_cloud_map.height,
                point_cloud_map.width,
                len(point_cloud_map.data),
            )

    except Exception as e:
        logging.error(
            "Exception occurred while getting SLAM mapping point cloud map: %s",
            e,

```

(continues on next page)

(continued from previous page)

```

    )

def close_slam():
    """Close SLAM system"""
    global robot, current_slam_mode
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Switch to idle mode to close SLAM
        status = controller.activate_slam_mode(magicbot.SlamMode.IDLE)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to close SLAM, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        current_slam_mode = "IDLE"
        logging.info("Successfully closed SLAM system")
    except Exception as e:
        logging.error("Exception occurred while closing SLAM: %s", e)

def recovery_stand():
    """Recovery stand"""
    global robot
    try:
        logging.info("=== Executing Recovery Stand ===")
        controller = robot.get_high_level_motion_controller()
        status = controller.set_gait(magicbot.GaitMode.GAIT_RECOVERY_STAND, 10000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to set robot gait, code: %s, message: %s",
                status.code,
                status.message,
            )
            return
    
```

(continues on next page)

(continued from previous page)

```

        logging.info("Successfully executed recovery stand")
        return
    except Exception as e:
        logging.error("Exception occurred while executing recovery stand: %s", e)
        return

def balance_stand():
    """Balance stand"""
    global robot
    try:
        logging.info("=== Executing Balance Stand ===")

        # Get high-level motion controller
        controller = robot.get_high_level_motion_controller()

        # Set gait to balance stand
        status = controller.set_gait(magicbot.GaitMode.GAIT_BALANCE_STAND, 10000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to set robot gait, code: %s, message: %s",
                status.code,
                status.message,
            )
            return False

        logging.info("Robot gait set to balance stand (supports movement)")
        return True

    except Exception as e:
        logging.error("Exception occurred while executing balance stand: %s", e)
        return False

def joystick_command(left_x_axis, left_y_axis, right_x_axis, right_y_axis):
    """Send joystick control command"""
    global robot
    try:
        # Get high-level motion controller

```

(continues on next page)

(continued from previous page)

```

        controller = robot.get_high_level_motion_controller()

        # Create joystick command
        joy_command = magicbot.JoystickCommand()
        joy_command.left_x_axis = left_x_axis
        joy_command.left_y_axis = left_y_axis
        joy_command.right_x_axis = right_x_axis
        joy_command.right_y_axis = right_y_axis

        # Send joystick command
        controller.send_joystick_command(joy_command)
    except Exception as e:
        logging.error("Exception occurred while sending joystick command: %s", e)

def move_forward():
    """Move forward"""
    logging.info("=== Moving Forward ===")
    return joystick_command(0.0, 1.0, 0.0, 0.0)

def move_backward():
    """Move backward"""
    logging.info("=== Moving Backward ===")
    return joystick_command(0.0, -1.0, 0.0, 0.0)

def move_left():
    """Move left"""
    logging.info("=== Moving Left ===")
    return joystick_command(-1.0, 0.0, 0.0, 0.0)

def move_right():
    """Move right"""
    logging.info("=== Moving Right ===")
    return joystick_command(1.0, 0.0, 0.0, 0.0)

def turn_left():

```

(continues on next page)

(continued from previous page)

```

    """Turn left"""
    logging.info("=== Turning Left ===")
    return joystick_command(0.0, 0.0, -1.0, 0.0)

def turn_right():
    """Turn right"""
    logging.info("=== Turning Right ===")
    return joystick_command(0.0, 0.0, 1.0, 0.0)

def stop_move():
    """Stop move"""
    logging.info("=== Stopping Move ===")
    return joystick_command(0.0, 0.0, 0.0, 0.0)

# ===== Utility Functions =====

# Get single character input (no echo)
def getch():
    fd = sys.stdin.fileno()
    old_settings = termios.tcgetattr(fd)
    try:
        tty.setraw(sys.stdin.fileno())
        ch = sys.stdin.read(1)
        logging.info(f"Received character: {ch}")

        sys.stdout.write("\r")
        sys.stdout.flush()
    finally:
        termios.tcsetattr(fd, termios.TCSADRAIN, old_settings)
    return ch

def get_user_input():
    """Get user input - Read a single line of data"""
    try:
        # Method 1: Read a line using input() (recommended)

```

(continues on next page)

(continued from previous page)

```

        return input("Enter command: ").strip()
    except (EOFError, KeyboardInterrupt):
        return ""

def main():
    """Main function"""
    global robot, running

    # Bind signal handler
    signal.signal(signal.SIGINT, signal_handler)

    logging.info("Robot model: %s", magicbot.get_robot_model())

    # Create robot instance
    robot = magicbot.MagicRobot()

    print_help()
    logging.info("Press any key to continue (ESC to exit)...")

    try:
        # Configure local IP address for direct network connection and initialize SDK
        local_ip = "192.168.54.111"
        if not robot.initialize(local_ip):
            logging.error("Failed to initialize robot SDK")
            robot.shutdown()
            return -1

        # Connect to robot
        status = robot.connect()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to connect to robot, code: %s, message: %s",
                status.code,
                status.message,
            )
            robot.shutdown()
            return -1

        logging.info("Successfully connected to robot")

```

(continues on next page)

(continued from previous page)

```
# Switch motion control controller to high-level controller
status = robot.set_motion_control_level(magicbot.ControllerLevel.HighLevel)
if status.code != magicbot.ErrorCode.OK:
    logging.error(
        "Failed to switch robot motion control level, code: %s, message: %s",
        status.code,
        status.message,
    )
    robot.shutdown()
    return -1

# Initialize SLAM navigation controller
slam_nav_controller = robot.get_slam_nav_controller()
if not slam_nav_controller.initialize():
    logging.error("Failed to initialize SLAM navigation controller")
    robot.disconnect()
    robot.shutdown()
    return -1

logging.info("Successfully initialized SLAM navigation controller")

# Main loop
while running:
    try:
        key = getch()
        if key == "\x1b": # ESC key
            break

        # 1. Preparation Functions
        # 1.1 Execute recovery stand first. Two mapping methods: 1) Suspended
        ↪ in air, can push robot for mapping in recovery_stand state; 2) Switch to balance_
        ↪ stand state for remote-controlled mapping
        if key.upper() == "Q":
            recovery_stand()
        elif key.upper() == "E":
            balance_stand()
        elif key.upper() == "W":
            move_forward()
        elif key.upper() == "A":
```

(continues on next page)



(continued from previous page)

```

        move_left()
    elif key.upper() == "S":
        move_backward()
    elif key.upper() == "D":
        move_right()
    elif key.upper() == "X":
        stop_move()
    elif key.upper() == "T":
        turn_left()
    elif key.upper() == "G":
        turn_right()
# 2. Mapping Mode
# 2.1 Switch to mapping mode
    elif key == "1":
        switch_to_mapping_mode()
# 2.2 Start mapping
    elif key == "2":
        start_mapping()
# 2.3 Cancel mapping
    elif key == "3":
        cancel_mapping()
# 2.4 Save map
    elif key == "4":
        save_map()
# 2.5 Load map
    elif key == "5":
        str_input = get_user_input()
        # Split input parameters by space
        parts = str_input.strip().split()
        # Parse parameters
        map_to_load = parts[0] if parts else ""
        load_map(map_to_load)
# 2.6 Delete map
    elif key == "6":
        str_input = get_user_input()
        # Split input parameters by space
        parts = str_input.strip().split()
        # Parse parameters
        map_to_delete = parts[0] if parts else ""
        delete_map(map_to_delete)

```

(continues on next page)

(continued from previous page)

```

# 2.7 Get all map information
elif key == "7":
    get_all_map_info()
# 2.8 Get map path
elif key.upper() == "8":
    str_input = get_user_input()
    # Split input parameters by space
    parts = str_input.strip().split()
    # Parse parameters
    map_to_get_path = parts[0] if parts else ""
    get_map_path(map_to_get_path)
# 2.9 Get SLAM mapping point cloud map
elif key.upper() == "9":
    get_point_cloud_map()
# 3. Close Functions
# 3.1 Close SLAM
elif key.upper() == "P":
    close_slam()
elif key.upper() == "?":
    print_help()
else:
    logging.warning("Unknown key: %s", key)

time.sleep(0.01) # Brief delay

except KeyboardInterrupt:
    break
except Exception as e:
    logging.error("Exception occurred while processing user input: %s", e)
except Exception as e:
    logging.error("Exception occurred during program execution: %s", e)
    return -1

finally:
    # Clean up resources
    try:
        logging.info("Clean up resources")
        # Close SLAM navigation controller
        slam_nav_controller = robot.get_slam_nav_controller()
        slam_nav_controller.shutdown()

```

(continues on next page)

(continued from previous page)

```

        logging.info("SLAM navigation controller closed")

        # Disconnect
        robot.disconnect()
        logging.info("Robot connection disconnected")

        # Shutdown robot
        robot.shutdown()
        logging.info("Robot shutdown")

    except Exception as e:
        logging.error("Exception occurred while cleaning up resources: %s", e)

if __name__ == "__main__":
    sys.exit(main())

```

## 26.2.2 Navigation Example

```

#!/usr/bin/env python3
# -*- coding: utf-8 -*-

import sys
import time
import signal
import threading
import logging
from typing import Optional
import numpy as np
import cv2
import random

import magicbot_z1_python as magicbot

# Configure logging format and level
logging.basicConfig(
    level=logging.INFO, # Minimum log level
    format="%(asctime)s [%(levelname)s] %(message)s",
    datefmt="%Y-%m-%d %H:%M:%S",
)

```

(continues on next page)

(continued from previous page)

```
# Global variables
robot: Optional[magicbot.MagicRobot] = None
running = True
current_slam_mode = None
current_nav_mode = magicbot.NavMode.IDLE
odometry_counter = 0

def signal_handler(signum, frame):
    """Signal handler function for graceful exit"""
    global running, robot
    logging.info("Received interrupt signal (%s), exiting...", signum)
    running = False
    if robot:
        robot.shutdown()
        logging.info("Robot shutdown")
    exit(-1)

def print_help():
    """Print help information"""
    logging.info("SLAM and Navigation Function Demo Program")
    logging.info("")
    logging.info("preparation Functions:")
    logging.info("  Q      Function Q: Recovery stand")
    logging.info("  W      Function W: Balance stand")
    logging.info("  E      Function E: Get map path")
    logging.info("")
    logging.info("Localization Functions:")
    logging.info("  1      Function 1: Switch to localization mode")
    logging.info("  2      Function 2: Initialize pose")
    logging.info("  3      Function 3: Get current pose information")
    logging.info("")
    logging.info("Navigation Functions:")
    logging.info("  4      Function 4: Switch to navigation mode")
    logging.info("  5      Function 5: Set navigation target goal")
    logging.info("  6      Function 6: Pause navigation")
    logging.info("  7      Function 7: Resume navigation")
    logging.info("  8      Function 8: Cancel navigation")
```

(continues on next page)

(continued from previous page)

```

logging.info(" 9      Function 9: Get navigation status")
logging.info("")
logging.info("Odometry Functions:")
logging.info(" Z      Function Z: Open odometry stream")
logging.info(" X      Function X: Close odometry stream")
logging.info(" C      Function C: Subscribe odometry stream")
logging.info(" V      Function V: Unsubscribe odometry stream")
logging.info("")
logging.info("Close Functions:")
logging.info(" P      Function P: Close SLAM")
logging.info(" L      Function L: Close navigation")
logging.info("")
logging.info(" ?      Function ?: Print help")
logging.info(" ESC    Exit program")

# ===== Navigation Functions =====
def get_map_path(map_to_get_path):
    """Get map path"""
    global robot
    try:
        if not map_to_get_path:
            logging.error("Map to get path is not provided")
            return

        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Get map path
        status, map_path = controller.get_map_path(map_to_get_path)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to get map path, code: %s, message: %s",
                status.code,
                status.message,
            )
            return
        if len(map_path) == 0:
            logging.error("No map path found")
            return

```

(continues on next page)

(continued from previous page)

```

    for path in map_path:
        logging.info("Map path: %s", path)
    except Exception as e:
        logging.error("Exception occurred while getting map path: %s", e)
    return

def switch_to_localization_mode(map_path):
    """Switch to localization mode"""
    global robot, current_slam_mode
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Switch to localization mode
        status = controller.activate_slam_mode(magicbot.SlamMode.LOCALIZATION, map_
↪path)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to switch to localization mode, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        current_slam_mode = "LOCALIZATION"
        logging.info("Successfully switched to localization mode")
        logging.info(
            "Robot is now in localization mode, ready to localize on existing maps"
        )
    except Exception as e:
        logging.error("Exception occurred while switching to localization mode: %s",
↪e)

def initialize_pose(x, y, yaw):
    """Initialize pose"""
    global robot
    try:
        # Get SLAM navigation controller

```

(continues on next page)

(continued from previous page)

```

controller = robot.get_slam_nav_controller()

# Create initial pose (set to origin)
initial_pose = magicbot.Pose3DEuler()
initial_pose.position = [x, y, 0.0] # x, y, z
initial_pose.orientation = [0.0, 0.0, yaw] # roll, pitch, yaw

logging.info("Initializing robot pose to origin...")

# Initialize pose
status = controller.init_pose(initial_pose)
if status.code != magicbot.ErrorCode.OK:
    logging.error(
        "Failed to initialize pose, code: %s, message: %s",
        status.code,
        status.message,
    )
    return

logging.info("Successfully initialized pose")
logging.info("Robot pose has been set to origin (0, 0, 0)")
except Exception as e:
    logging.error("Exception occurred while initializing pose: %s", e)

def get_current_localization_info():
    """Get current pose information"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Get current pose information
        status, pose_info = controller.get_current_localization_info()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to get current pose information, code: %s, message: %s",
                status.code,
                status.message,
            )

```

(continues on next page)

(continued from previous page)

```

        return

    logging.info("Successfully retrieved current pose information")
    logging.info(
        "Localization status: %s",
        "Localized" if pose_info.is_localization else "Not localized",
    )
    logging.info(
        "Position: [%.3f, %.3f, %.3f]",
        pose_info.pose.position[0],
        pose_info.pose.position[1],
        pose_info.pose.position[2],
    )
    logging.info(
        "Orientation: [%.3f, %.3f, %.3f]",
        pose_info.pose.orientation[0],
        pose_info.pose.orientation[1],
        pose_info.pose.orientation[2],
    )
except Exception as e:
    logging.error(
        "Exception occurred while getting current pose information: %s", e
    )

def switch_to_navigation_mode(map_path):
    """Switch to navigation mode"""
    global robot, current_nav_mode
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Switch to navigation mode
        status = controller.activate_nav_mode(magicbot.NavMode.GRID_MAP, map_path)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to switch to navigation mode, code: %s, message: %s",
                status.code,
                status.message,
            )
    
```

(continues on next page)



(continued from previous page)

```

        return

    current_nav_mode = magicbot.NavMode.GRID_MAP
    logging.info("Successfully switched to navigation mode")
except Exception as e:
    logging.error("Exception occurred while switching to navigation mode: %s", e)

def set_navigation_target(x, y, yaw):
    """Set navigation target goal"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Create target goal
        target_goal = magicbot.NavTarget()
        target_goal.id = 1
        target_goal.frame_id = "map"

        # Set target pose (example: move 2 meters forward)
        target_goal.goal.position = [x, y, 0.0]
        # Set target orientation (example: no rotation)
        target_goal.goal.orientation = [0.0, 0.0, yaw]

        # Set target goal
        status = controller.set_nav_target(target_goal)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to set navigation target, code: %s, message: %s",
                status.code,
                status.message,
            )
        return

    logging.info(
        "Successfully set navigation target: position=(%.2f, %.2f, %.2f), ↵
↪orientation=(%.2f, %.2f, %.2f)",
        target_goal.goal.position[0],
        target_goal.goal.position[1],

```

(continues on next page)

(continued from previous page)

```

        target_goal.goal.position[2],
        target_goal.goal.orientation[0],
        target_goal.goal.orientation[1],
        target_goal.goal.orientation[2],
    )
except Exception as e:
    logging.error("Exception occurred while setting navigation target: %s", e)

def pause_navigation():
    """Pause navigation"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Pause navigation
        status = controller.pause_nav_task()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to pause navigation, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        logging.info("Successfully paused navigation")
    except Exception as e:
        logging.error("Exception occurred while pausing navigation: %s", e)

def resume_navigation():
    """Resume navigation"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Resume navigation
        status = controller.resume_nav_task()

```

(continues on next page)

(continued from previous page)

```

    if status.code != magicbot.ErrorCode.OK:
        logging.error(
            "Failed to resume navigation, code: %s, message: %s",
            status.code,
            status.message,
        )
        return

    logging.info("Successfully resumed navigation")
except Exception as e:
    logging.error("Exception occurred while resuming navigation: %s", e)

def cancel_navigation():
    """Cancel navigation"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Cancel navigation
        status = controller.cancel_nav_task()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to cancel navigation, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        logging.info("Successfully cancelled navigation")
    except Exception as e:
        logging.error("Exception occurred while cancelling navigation: %s", e)

def get_navigation_status():
    """Get current navigation status"""
    global robot
    try:
        # Get SLAM navigation controller

```

(continues on next page)

(continued from previous page)

```

controller = robot.get_slam_nav_controller()

# Get navigation status
status, nav_status = controller.get_nav_task_status()
if status.code != magicbot.ErrorCode.OK:
    logging.error(
        "Failed to get navigation status, code: %s, message: %s",
        status.code,
        status.message,
    )
    return

# Display navigation status information
logging.info("=== Navigation Status ===")
logging.info("Target ID: %d", nav_status.id)
logging.info("Status: %s", nav_status.status)
logging.info("Error Code: %d", nav_status.error_code)
logging.info("Error Description: %s", nav_status.error_desc)

# Provide status interpretation
status_meaning = {
    magicbot.NavStatusType.NONE: "No navigation target set",
    magicbot.NavStatusType.RUNNING: "Navigation is running",
    magicbot.NavStatusType.END_SUCCESS: "Navigation completed successfully",
    magicbot.NavStatusType.END_FAILED: "Navigation failed",
    magicbot.NavStatusType.PAUSE: "Navigation is paused",
    magicbot.NavStatusType.CONTINUE: "Navigation resumed from pause",
    magicbot.NavStatusType.CANCEL: "Navigation was cancelled",
}

if nav_status.status in status_meaning:
    logging.info("Status meaning: %s", status_meaning[nav_status.status])
else:
    logging.warning("Unknown status value: %s", nav_status.status)

logging.info("=====")

except Exception as e:
    logging.error("Exception occurred while getting navigation status: %s", e)

```

(continues on next page)

(continued from previous page)

```
def close_navigation():
    """Close navigation system"""
    global robot, current_nav_mode
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Switch to idle mode to close navigation
        status = controller.activate_nav_mode(magicbot.NavMode.IDLE)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to close navigation, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        current_nav_mode = magicbot.NavMode.IDLE
        logging.info("Successfully closed navigation system")
    except Exception as e:
        logging.error("Exception occurred while closing navigation: %s", e)

def open_odometry_stream():
    """Open odometry stream"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Open odometry stream
        status = controller.open_odometry_stream()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to open odometry stream, code: %s, message: %s",
                status.code,
                status.message,
            )
            return
```

(continues on next page)

(continued from previous page)

```

        logging.info("Successfully opened odometry stream")
    except Exception as e:
        logging.error("Exception occurred while opening odometry stream: %s", e)

def close_odometry_stream():
    """Close odometry stream"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Close odometry stream
        status = controller.close_odometry_stream()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to close odometry stream, code: %s, message: %s",
                status.code,
                status.message,
            )
        return
        logging.info("Successfully closed odometry stream")
    except Exception as e:
        logging.error("Exception occurred while closing odometry stream: %s", e)

def subscribe_odometry_stream():
    """Subscribe odometry stream"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        def callback(odometry: magicbot.Odometry):
            global odometry_counter
            if odometry_counter % 30 == 0:
                logging.info(
                    "Odometry position: %f, %f, %f",
                    odometry.position[0],
                    odometry.position[1],

```

(continues on next page)

(continued from previous page)

```

        odometry.position[2],
    )
    logging.info(
        "Odometry orientation: %f, %f, %f, %f",
        odometry.orientation[0],
        odometry.orientation[1],
        odometry.orientation[2],
        odometry.orientation[3],
    )
    logging.info(
        "Odometry linear velocity: %f, %f, %f",
        odometry.linear_velocity[0],
        odometry.linear_velocity[1],
        odometry.linear_velocity[2],
    )
    logging.info(
        "Odometry angular velocity: %f, %f, %f",
        odometry.angular_velocity[0],
        odometry.angular_velocity[1],
        odometry.angular_velocity[2],
    )
    odometry_counter += 1

    # Subscribe odometry stream
    controller.subscribe_odometry(callback)
    logging.info("Successfully subscribed odometry stream")
except Exception as e:
    logging.error("Exception occurred while subscribing odometry stream: %s", e)

def unsubscribe_odometry_stream():
    """Unsubscribe odometry stream"""
    global robot
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Unsubscribe odometry stream
        controller.unsubscribe_odometry()
        logging.info("Successfully unsubscribed odometry stream")

```

(continues on next page)

(continued from previous page)

```

except Exception as e:
    logging.error("Exception occurred while unsubscribing odometry stream: %s", e)

def close_slam():
    """Close SLAM system"""
    global robot, current_slam_mode
    try:
        # Get SLAM navigation controller
        controller = robot.get_slam_nav_controller()

        # Switch to idle mode to close SLAM
        status = controller.activate_slam_mode(magicbot.SlamMode.IDLE)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to close SLAM, code: %s, message: %s",
                status.code,
                status.message,
            )
            return

        current_slam_mode = "IDLE"
        logging.info("Successfully closed SLAM system")
    except Exception as e:
        logging.error("Exception occurred while closing SLAM: %s", e)

def recovery_stand():
    """Recovery stand"""
    global robot
    try:
        logging.info("=== Executing Recovery Stand ===")
        controller = robot.get_high_level_motion_controller()
        status = controller.set_gait(magicbot.GaitMode.GAIT_RECOVERY_STAND, 10000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to set robot gait, code: %s, message: %s",
                status.code,
                status.message,
            )

```

(continues on next page)



(continued from previous page)

```

        return
    logging.info("Successfully executed recovery stand")
    return
except Exception as e:
    logging.error("Exception occurred while executing recovery stand: %s", e)
    return

def balance_stand():
    """Balance stand"""
    global robot
    try:
        logging.info("=== Executing Balance Stand ===")
        controller = robot.get_high_level_motion_controller()
        status = controller.set_gait(magicbot.GaitMode.GAIT_BALANCE_STAND, 10000)
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to set robot gait, code: %s, message: %s",
                status.code,
                status.message,
            )
            return
        logging.info("Successfully executed balance stand")
        return
    except Exception as e:
        logging.error("Exception occurred while executing balance stand: %s", e)
        return

# ===== Utility Functions =====

def get_user_input():
    """Get user input - Read a single line of data"""
    try:
        # Method 1: Read a line using input() (recommended)
        return input("Enter command: ").strip()
    except (EOFError, KeyboardInterrupt):
        return ""

```

(continues on next page)

(continued from previous page)

```

def main():
    """Main function"""
    global robot, running

    # Bind signal handler
    signal.signal(signal.SIGINT, signal_handler)

    logging.info("Robot model: %s", magicbot.get_robot_model())

    # Create robot instance
    robot = magicbot.MagicRobot()

    print_help()
    logging.info("Press any key to continue (ESC to exit)...")

    try:
        # Configure local IP address for direct network connection and initialize SDK
        local_ip = "192.168.54.111"
        if not robot.initialize(local_ip):
            logging.error("Failed to initialize robot SDK")
            robot.shutdown()
            return -1

        # Connect to robot
        status = robot.connect()
        if status.code != magicbot.ErrorCode.OK:
            logging.error(
                "Failed to connect to robot, code: %s, message: %s",
                status.code,
                status.message,
            )
            robot.shutdown()
            return -1

        logging.info("Successfully connected to robot")

        # Switch motion control controller to high-level controller
        status = robot.set_motion_control_level(magicbot.ControllerLevel.HighLevel)
        if status.code != magicbot.ErrorCode.OK:

```

(continues on next page)

(continued from previous page)

```

logging.error(
    "Failed to switch robot motion control level, code: %s, message: %s",
    status.code,
    status.message,
)
robot.shutdown()
return -1

logging.info("Successfully switched robot motion control level to high-level")

# Initialize SLAM navigation controller
slam_nav_controller = robot.get_slam_nav_controller()
if not slam_nav_controller.initialize():
    logging.error("Failed to initialize SLAM navigation controller")
    robot.disconnect()
    robot.shutdown()
    return -1

logging.info("Successfully initialized SLAM navigation controller")

# Main loop
while running:
    try:
        str_input = get_user_input()

        # Split input parameters by space
        parts = str_input.strip().split()

        if not parts:
            time.sleep(0.01) # Brief delay
            continue

        # Parse parameters
        key = parts[0]
        args = parts[1:] if len(parts) > 1 else []
        if key == "\x1b": # ESC key
            break

        # 1. Preparation
        # 1.1 Execute recovery stand first

```

(continues on next page)

(continued from previous page)

```

    if key.upper() == "Q":
        recovery_stand()
        # 1.2 Switch to balance stand, allowing robot to transition to_
↪walking gait
    elif key.upper() == "W":
        balance_stand()
        # 1.3 Get current map absolute path
    elif key.upper() == "E":
        map_to_get_path = args[0] if args else ""
        get_map_path(map_to_get_path)
        # 2. Enable Localization Mode and Initialize Pose
        # 2.2 Based on map absolute path, enable localization mode
    elif key == "1":
        map_path = args[0] if args else ""
        switch_to_localization_mode(map_path)
        # 2.3 Based on current map, initialize pose
    elif key == "2":
        x = float(args[0]) if args else 0.0
        y = float(args[1]) if args else 0.0
        yaw = float(args[2]) if args else 0.0
        logging.info("input pose, x: %f, y: %f, yaw: %f", x, y, yaw)
        initialize_pose(x, y, yaw)
        # 2.4 Get current initialized pose status, check if localization_
↪succeeded

    elif key == "3":
        get_current_localization_info()
        # 3. Start Navigation
        # 3.1 Based on map absolute path, enable navigation mode
    elif key.upper() == "4":
        map_path = args[0] if args else ""
        switch_to_navigation_mode(map_path)
        # 3.2 Input target point, start navigation task
        # Due to the lidar being installed with a -1.57rad offset relative to_
↪the robot's front,
        # the desired yaw orientation needs to be offset by -1.57rad,
↪otherwise the robot's pose initialization may fail
        # Please input yaw orientation, needs to be offset by -1.57rad
    elif key.upper() == "5":
        x = float(args[0]) if args else 0.0
        y = float(args[1]) if args else 0.0

```

(continues on next page)

(continued from previous page)

```

        yaw = float(args[2]) if args else 0.0
        logging.info("input target, x: %f, y: %f, yaw: %f", x, y, yaw)
        set_navigation_target(x, y, yaw)
    # 3.3 Pause navigation task
    elif key.upper() == "6":
        pause_navigation()
    # 3.4 Resume navigation task
    elif key.upper() == "7":
        resume_navigation()
    # 3.5 Cancel navigation task
    elif key.upper() == "8":
        cancel_navigation()
    # 3.6 Get navigation task status
    elif key.upper() == "9":
        get_navigation_status()
    # 4. Subscribe to Odometry Data
    # 4.1 Open odometry stream
    elif key.upper() == "Z":
        open_odometry_stream()
    # 4.2 Close odometry stream
    elif key.upper() == "X":
        close_odometry_stream()
    # 4.3 Subscribe to odometry stream
    elif key.upper() == "C":
        subscribe_odometry_stream()
    # 4.4 Unsubscribe from odometry stream
    elif key.upper() == "V":
        unsubscribe_odometry_stream()
    # 5. Close SLAM and Navigation
    # 5.1 Close SLAM
    elif key.upper() == "P":
        close_slam()
    # 5.2 Close navigation
    elif key.upper() == "L":
        close_navigation()
    elif key.upper() == "?":
        print_help()
    else:
        logging.warning("Unknown key: %s", key)

```

(continues on next page)

(continued from previous page)

```

        time.sleep(0.01)  # Brief delay

    except KeyboardInterrupt:
        break
    except Exception as e:
        logging.error("Exception occurred while processing user input: %s", e)
except Exception as e:
    logging.error("Exception occurred during program execution: %s", e)
    return -1

finally:
    # Clean up resources
    try:
        logging.info("Clean up resources")
        # Close SLAM navigation controller
        slam_nav_controller = robot.get_slam_nav_controller()
        slam_nav_controller.shutdown()
        logging.info("SLAM navigation controller closed")

        # Disconnect
        robot.disconnect()
        logging.info("Robot connection disconnected")

        # Shutdown robot
        robot.shutdown()
        logging.info("Robot shutdown")

    except Exception as e:
        logging.error("Exception occurred while cleaning up resources: %s", e)

if __name__ == "__main__":
    sys.exit(main())

```

## 26.3 Running Instructions

### 26.3.1 Environment Setup

```
export PYTHONPATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$PYTHONPATH
export LD_LIBRARY_PATH=/opt/magic_robotics/magicbot_z1_sdk/lib:$LD_LIBRARY_PATH
```

### 26.3.2 Run Examples

```
# C++
./slam_navigation_example
# Python
python3 slam_navigation_example.py
```

### 26.3.3 Control Instructions

#### Mapping

- Preparation Functions:
  - Press Q - Recovery stand
  - Press E - Balance stand
  - Press W/A/S/D/X - Forward/Left/Backward/Right/Stop
  - Press T/G - Turn left/Turn right
- SLAM Functions:
  - Press 1 - Switch to mapping mode
  - Press 2 - Start mapping
  - Press 3 - Cancel mapping
  - Press 4 - Save map
  - Press 5 - Load map
  - Press 6 - Delete map
  - Press 7 - Get all map information and save map image as PGM file
  - Press 8 - Get map path
  - Press 9 - Get SLAM mapping point cloud map
- Close Functions:
  - Press P - Close SLAM

- System Commands:
  - Press ? - Show help information

## Navigation

- Preparation Functions:
  - Press Q - Recovery stand
  - Press W - Balance stand
  - Press E - Get map path
- Localization Functions:
  - Press 1 - Switch to localization mode
  - Press 2 - Initialize pose
  - Press 3 - Get current position information
- Navigation Functions:
  - Press 4 - Switch to navigation mode
  - Press 5 - Set navigation target goal
  - Press 6 - Pause navigation
  - Press 7 - Resume navigation
  - Press 8 - Cancel navigation
  - Press 9 - Get navigation status
- Odometry Functions:
  - Press Z - Open odometry stream
  - Press X - Close odometry stream
  - Press C - Subscribe odometry stream
  - Press V - Unsubscribe odometry stream
- Close Functions:
  - Press P - Close SLAM
  - Press L - Close navigation
- System Commands:
  - Press ? - Show help information



### 26.3.4 Stop Program

- Press `ESC` to safely stop the program
- The program will automatically clean up all resources

### 26.3.5 Notes

- In the mapping and navigation examples, the robot must be switched to high-level motion control mode in advance (the default control mode is high-level motion control).
- In the mapping example, the robot should be switched to `Balance_stand` mode in advance.
- In the mapping example, you can use `GetAllMapInfo` to get information about maps stored on the robot (including 2D map PGM, map size, resolution, etc.).
- In the mapping example, you can manage maps using `SaveMap/DeleteMap`. Try not to store more than 3 maps on the robot.
- In the navigation example, you need to switch the robot to `Balance_stand` mode first.
- In the navigation example, it's best to set navigation target points based on the current localization status and pose obtained from `GetCurrentLocalizationInfo`.
- In the navigation example, before starting navigation tasks, you need to properly switch to localization mode (`ActivateSlamMode(SlamMode::LOCALIZATION, map_path)`) and navigation mode (`ActivateNavMode(NavMode::GRID_MAP, map_path)`).
- In the navigation example, both localization mode and navigation mode switches require the absolute path of the map, which can be obtained using `GetMapPath`.
- After finishing mapping or navigation, switch SLAM to `IDLE` mode (`ActivateSlamMode(SlamMode::IDLE)`) and navigation to `IDLE` mode (`ActivateNavMode(NavMode::IDLE)`)



---

When the SDK becomes unavailable, first verify whether the SDK version meets the requirements. The SDK version tag must correspond to the robot firmware version. Refer to [ChangeLog](#)

### 27.1 Development Environment Preparation

Operating System: Ubuntu 22.04. For detailed setup, please refer to Quick Start.

### 27.2 Does Magicbot-Z1 support wireless development?

No. Magicbot-Z1 currently supports only wired connections for development.

### 27.3 What is the current low-level communication frequency of Magicbot-Z1?

The default reporting frequency for joint status communication at the low level is 500 Hz. The publishing frequency (Suggested frequency: 500 Hz) of joint command transmission is controlled by the user.

## 27.4 Unable to Subscribe and Publish Topic Data?

- Check whether the corresponding topic data stream is enabled.

Some interfaces require calling a specific function to activate the data stream, such as calling `OpenLidar` to enable LiDAR data.

- UDP multicast configuration:

Assuming the network interface connecting the SDK development PC and the robot is `enp0s31f6`, configure it as follows to ensure communication between the SDK and the robot at the low level:

```
sudo ifconfig enp0s31f6 multicast
sudo route add -net 224.0.0.0 netmask 240.0.0.0 dev enp0s31f6
```

- SDK version does not match the robot firmware version:

The SDK version tag must correspond to the robot's firmware version. For reference, see: [ChangeLog](#).

- Clean residual SDK configuration files:

The SDK automatically generates its default configuration at `/tmp/magicbot_z1_mjrrt.yaml`. Under normal circumstances, this file is cleared on reboot. However, if during a single boot you first use an older version of the SDK (which generates an old configuration file in `/tmp`), and then switch to a newer SDK version, the newer SDK will still load the old configuration by default. This is because if the `magicbot_z1_mjrrt.yaml` file already exists, the SDK will not recreate it, in order to facilitate debugging. As a result, topic subscription and publication may behave incorrectly.

Finally, please note that when using subscription-type SDK interfaces such as `Subscribe`, avoid performing blocking operations within the callback function. Otherwise, it may lead to message backlog, processing delays, or even unexpected errors.

## 27.5 SDK subscription topic data rate unstable?

Check the system configuration of the socket receive buffer on the SDK host in `/etc/sysctl.conf`. Apply the changes immediately using `sysctl -p`, or reboot the host.

```
net.core.rmem_max=20971520
net.core.rmem_default=20971520
net.core.wmem_max=20971520
net.core.wmem_default=20971520
```

## 27.6 SDK API Call Error: Deadline Exceeded

The default timeout for internal RPC calls within the SDK APIs is 5 seconds. For certain gait or skill execution APIs, the execution time may exceed 5 seconds. If this issue occurs, you can resolve it by configuring the timeout parameter for the specific API.

## 27.7 How to View SDK Internal Configuration and Logs?

When the SDK program is executed, it will by default generate a configuration file at `/tmp/magicbot_z1_mjrrt.yaml` and a log file at `/tmp/logs/magicbot_z1_sdk.log`. Any internal error messages of the SDK can be checked in this log file.

## 27.8 Video Streaming

How to access binocular camera video stream:

```
# Wireless (requires connecting to the robot's hotspot)
ffplay rtsp://192.168.12.1:8081/
# Wired
ffplay rtsp://192.168.54.119:8081/
```

You can use `ffplay` for testing during demonstration. If you want to capture individual frames, you need to implement your own encoding.

## 27.9 SLAM Relocation Failed?

SLAM navigation via SDK differs from the App' s convenient visual localization. You need to modify the SLAM configuration to fix the map orientation for easier SLAM localization:

```
# Log into the robot
ssh eame@192.168.54.119
# Modify the following configuration
# vim /opt/eame/eamegrapher_3d/share/eamegrapher_3d/config/params.yaml
align_map: false

# After modifying the yaml file for the first time, restart the SLAM module for
↳ changes to take effect with:
sudo systemctl restart slam.service
```

## 27.10 SLAM Navigation Not Executing?

1. First prerequisite for SLAM navigation - enter SLAM localization mode and navigation mode:

- `ActivateSlamMode(SlamMode::LOCALIZATION, map_path)`
- `ActivateNavMode(NavMode::GRID_MAP, map_path)`

Where `map_path` is the absolute path to the current map, which can be obtained via `GetMapPath`

2. Second prerequisite for SLAM navigation - successful relocation:

Use `InitPose` for relocation and call `GetCurrentLocalizationInfo` to get current relocation status. If `is_localization=true`, relocation is successful; otherwise, relocation failed - check map and relocation pose, then retry `InitPose` for localization.

3. Setting SLAM navigation target points:

Since the relocation pose set by `InitPose` is estimated, it is recommended to set target position points based on the current pose obtained from `GetCurrentLocalizationInfo`.

## 27.11 Runtime Error: Invalid IP address

The current robot does not support simultaneous control by an APP and SDK, nor does it support multiple SDK clients controlling the robot at the same time. If an `Invalid IP address` error occurs, please check if there are other APPs or SDK clients connected.

## 27.12 Log Error: Call of `pthread_setschedparam` with insufficient privileges!

The main reason for this error is that the SDK is being executed with a regular user account. This warning does not fundamentally affect program operation. To resolve this error, you need to configure the system file `/etc/security/limits.conf` for the regular user to ensure the process has permission to set thread priorities:

```
*      -      rtprio    98
```

## 27.13 connect Error: Failed to connect to robot, code: `ErrorCode.SERVICE_ERROR`, message: failed to connect to all addresses; last error: UNKNOWN: ipv4:192.168.54.119:50051: Failed to connect to remote host: Connection refused

1. Unable to ping `192.168.54.119`:

- Network cable connection problem, check hardware connections.
- The compute box IP configuration is not in the 192.168.54.XX subnet.

2. Robot gateway service exception:

- Try restarting to restore normal robot software operation.

## 27.14 Trick Execution Error: Failed to execute robot trick, code: `ErrorCode.SERVICE_ERROR`, message: 优先级过低

Reason 1: The trick command ID called is not within the `TrickAction` enumeration range.

Reason 2: The robot needs to be on the ground and must switch to the `balance_stand` gait.

Note: For humanoid robots, the robot must first land on the ground in the `recovery_stand` state. After landing, switch to `balance_stand`, and then you can perform tricks and other actions.

## 27.15 Trick Execution Error: Failed to execute robot trick, code: `ErrorCode.SERVICE_ERROR`, message: 危险动作

The possible reason for this error may be that the robot's current initial position differs greatly from the required starting position for the trick.

Solution:

- Try executing `recovery_stand` and then `balance_stand` in order to restore and retry.

## 27.16 Trick Execution Error: Failed to execute robot trick, code: `ErrorCode.SERVICE_ERROR`, message: 调用 ROS2 服务失败

Possible cause: There is an exception in the internal software service of the robot.

Solution:

- Restart the robot to try to recover. If restarting does not work, please contact after-sales support.